

FlyCapture 2.1 Managed API Programming Reference

Revised September 16, 2010

Point Grey Research Inc.

12051 Riverside Way • Richmond, BC • Canada • V6W 1K7 • **T** (604) 242-9937 • **www.ptgrey.com**

Software Warranty

Point Grey Research warrants to the Original Purchaser, for a period of one (1) year from date of purchase that:

- 1. The diskette on which the Software is furnished and the accompanying documentation are not defective:
- 2. The Software is properly recorded upon the diskettes enclosed;
- 3. The documentation is substantially complete and contains all the information Point Grey Research deems necessary to use the Software;
- 4. The Software functions substantially as described in the documentation.

Point Grey Research, Inc.'s entire liability and the Original Purchaser's exclusive remedy shall be the replacement of any diskette or documentation not meeting these warranties. On such an occasion, a copy of the paid receipt accompanied with the faulty diskette or documentation must be returned to Point Grey Research, Inc. or an authorized dealer.

Point Grey Research, Inc. expressly disclaims and excludes all other warranties, express, implied and statutory, including, but without limitation, warranty of merchantability and fitness for a particular application or purpose. In no event shall Point Grey Research, Inc. be liable to the Original Purchaser or any third party for direct, indirect, incidental, consequential, special or accidental damages, including without limitation damages for business interruption, loss of profits, revenue, data or bodily injury or death.

Software License Agreement

The FlyCapture[®] Software Development Kit (the "Software") is owned and copyrighted by Point Grey Research, Inc. All rights are reserved. The Original Purchaser is granted a license to use the Software subject to the following restrictions and limitations.

- 1. The license is to the Original Purchaser only, and is nontransferable unless you have received written permission of Point Grey Research, Inc.
- 2. The Original Purchaser may use the Software only with Point Grey Research, Inc. cameras owned by the Original Purchaser, including but not limited to, Firefly®, Firefly®2, Firefly® MV, Flea®, ScorpionTM, Dragonfly®, Dragonfly®2, Dragonfly ExpressTM, GrasshopperTM or ChameleonTM Camera Modules.
- 3. The Original Purchaser may make back-up copies of the Software for his or her own use only, subject to the use limitations of this license.
- 4. Subject to s.5 below, the Original Purchaser may not engage in, nor permit third parties to engage in, any of the following:
 - A. Providing or disclosing the Software to third parties.
 - B. Making alterations or copies of any kind of the Software (except as specifically permitted in s.3 above).
 - C. Attempting to un-assemble, de-compile or reverse engineer the Software in any way.
 - D. Granting sublicenses, leases or other rights in the Software to others.
- 5. Original Purchasers who are Original Equipment Manufacturers may make Derivative Products with the Software. Derivative Products are new software products developed, in whole or in part, using the Software and other Point Grey Research, Inc. products. Point Grey Research, Inc. hereby grants a license to Original Equipment Manufacturers to incorporate and distribute the libraries found in the Software with the Derivative Products. The components of any Derivative Product that contain the Software libraries may only be used with Point Grey Research, Inc. products, or images derived from such products.
- 5.1 By the distribution of the Software libraries with Derivative Products, Original Purchasers agree to:
 - A. not permit further redistribution of the Software libraries by end-user customers;
 - B. include a valid copyright notice on any Derivative Product; and
 - C. indemnify, hold harmless, and defend Point Grey Research, Inc. from and against any claims or lawsuits, including attorney's fees, that arise or result from the use or distribution of any Derivative Product.

Point Grey Research, Inc. reserves the right to terminate this license if there are any violations of its terms or if there is a default committed by the Original Purchaser. Upon termination, for any reason, all copies of the Software must be immediately returned to Point Grey Research, Inc. and the Original Purchaser shall be liable to Point Grey Research, Inc. for any and all damages suffered as a result of the violation or default.

Contents

1	Mod	lule Ind	lex		1
	1.1	Modul	les		1
2	Nan	nespace	Index		3
	2.1	Names	space List		3
3	Clas	s Index			5
	3.1	Class l	Hierarchy		5
4	Clas	s Index	ī.		7
	4.1	Class l	List		7
5	Mod	lule Do	cumentatio	on	9
	5.1	Enume	erations .		9
		5.1.1	Enumera	tion Type Documentation	15
			5.1.1.1		15
			5.1.1.2	BayerTileFormat	16
			5.1.1.3	•	16
			5.1.1.4		17
			5.1.1.5	•	17
			5.1.1.6		17
			5.1.1.7		18
			5.1.1.8	GigEPropertyType	19
			5.1.1.9		19
			5.1.1.10	GrabTimeout	19
			5.1.1.11	ImageFileFormat	20
			5.1.1.12	InterfaceType	20
			5.1.1.13		20
			5.1.1.14		21
			5.1.1.15	OSType	22

ii CONTENTS

			5.1.1.16 PixelFormat	22
			5.1.1.17 PropertyType	22
			5.1.1.18 StatisticsChannel	23
			5.1.1.19 VideoMode	24
	5.2	Structi	ures	25
	5.3	Image	saving structures.	27
		5.3.1	Detailed Description	27
6	Nam	necnace	Documentation	29
v	6.1		pture2 Namespace Reference	29
	6.2		pture2Managed Namespace Reference	30
	0.2	6.2.1	Function Documentation	39
		0.2.1	6.2.1.1 EnumCallback	39
			6.2.1.2 ImageCallbackDelegate	39
			6.2.1.3 ImageEventCallback	39
	6.3	FlyCo	pture2Managed::Gui Namespace Reference	40
	0.5	TiyCa	pturezivianageuGui Tranicspace Reference	70
7	Clas	s Docu	mentation	41
	7.1	AviOp	otion Struct Reference	41
		7.1.1	Detailed Description	41
		7.1.2	Constructor & Destructor Documentation	41
			7.1.2.1 AviOption	41
		7.1.3	Property Documentation	41
			7.1.3.1 frameRate	41
	7.2	Camer	raControlDialog Class Reference	42
		7.2.1	Detailed Description	42
		7.2.2	Constructor & Destructor Documentation	42
			7.2.2.1 CameraControlDialog	42
			7.2.2.2 ~CameraControlDialog	42
		7.2.3	Member Function Documentation	42
			7.2.3.1 Connect	42
			7.2.3.2 Disconnect	42
			7.2.3.3 Hide	42
			7.2.3.4 IsVisible	42
			7.2.3.5 Show	42
	7.3	Camer	raInfo Struct Reference	43
		7.3.1	Detailed Description	44

	7.3.2	Property 1	Documentation	44
		7.3.2.1	bayerTileFormat	44
		7.3.2.2	configROM	44
		7.3.2.3	defaultGateway	44
		7.3.2.4	driverName	45
		7.3.2.5	firmwareBuildTime	45
		7.3.2.6	firmwareVersion	45
		7.3.2.7	gigEMajorVersion	45
		7.3.2.8	gigEMinorVersion	45
		7.3.2.9	iidcVersion	45
		7.3.2.10	interfaceType	45
		7.3.2.11	ipAddress	45
		7.3.2.12	isColorCamera	45
		7.3.2.13	macAddress	45
		7.3.2.14	maximumBusSpeed	45
		7.3.2.15	modelName	46
		7.3.2.16	sensorInfo	46
		7.3.2.17	sensorResolution	46
		7.3.2.18	serialNumber	46
		7.3.2.19	subnetMask	46
		7.3.2.20	userDefinedName	46
		7.3.2.21	vendorName	46
		7.3.2.22	xmlURL1	46
		7.3.2.23	xmlURL2	46
7.4	Camer	aProperty S	Struct Reference	47
	7.4.1	Detailed l	Description	47
	7.4.2	Construct	for & Destructor Documentation	48
		7.4.2.1	CameraProperty	48
		7.4.2.2	CameraProperty	48
	7.4.3	Property 1	Documentation	48
		7.4.3.1	absControl	48
		7.4.3.2	absValue	48
		7.4.3.3	autoManualMode	48
		7.4.3.4	onePush	48
		7.4.3.5	onOff	48
		7.4.3.6	present	48

iv CONTENTS

		7.4.3.7 type	18
		7.4.3.8 valueA	18
		7.4.3.9 valueB	18
7.5	Camer	aPropertyInfo Struct Reference	19
	7.5.1	Detailed Description	50
	7.5.2	Constructor & Destructor Documentation	50
		7.5.2.1 CameraPropertyInfo	50
		7.5.2.2 CameraPropertyInfo	60
	7.5.3	Property Documentation	60
		7.5.3.1 absMax	0
		7.5.3.2 absMin	0
		7.5.3.3 absValSupported	0
		7.5.3.4 autoSupported	0
		7.5.3.5 manualSupported	0
		7.5.3.6 max	0
		7.5.3.7 min	0
		7.5.3.8 onePushSupported	51
		7.5.3.9 onOffSupported	51
		7.5.3.10 present	51
		7.5.3.11 readOutSupported	51
		7.5.3.12 type	51
		7.5.3.13 unitAbbr	51
		7.5.3.14 units	51
7.6	Camer	aSelectionDialog Class Reference	52
	7.6.1	Detailed Description	52
	7.6.2	Constructor & Destructor Documentation	52
		7.6.2.1 CameraSelectionDialog	52
		7.6.2.2 ~CameraSelectionDialog	52
	7.6.3	Member Function Documentation	52
		7.6.3.1 GetSelectedCameraGuids	52
		7.6.3.2 ShowModal	52
7.7	Config	ROM Struct Reference	3
	7.7.1	Detailed Description	3
	7.7.2	Property Documentation	3
		7.7.2.1 chipIdHi	3
		7.7.2.2 chipIdLo	54

		7.7.2.3	keyword	54
		7.7.2.4	nodeVendorId	54
		7.7.2.5	unitSpecId	54
		7.7.2.6	unitSubSWVer	54
		7.7.2.7	unitSWVer	54
		7.7.2.8	vendorUniqueInfo0	54
		7.7.2.9	vendorUniqueInfo1	54
		7.7.2.10	vendorUniqueInfo2	54
		7.7.2.11	vendorUniqueInfo3	54
7.8	Embed	dedImage	Info Struct Reference	55
	7.8.1	Detailed	Description	55
	7.8.2	Construc	tor & Destructor Documentation	56
		7.8.2.1	EmbeddedImageInfo	56
	7.8.3	Property	Documentation	56
		7.8.3.1	brightness	56
		7.8.3.2	exposure	56
		7.8.3.3	frameCounter	56
		7.8.3.4	gain	56
		7.8.3.5	GPIOPinState	56
		7.8.3.6	ROIPosition	56
		7.8.3.7	shutter	56
		7.8.3.8	strobePattern	56
		7.8.3.9	timestamp	56
		7.8.3.10	whiteBalance	56
7.9	Embed	dedImage	InfoProperty Struct Reference	57
	7.9.1	Detailed	Description	57
	7.9.2	Property	Documentation	57
		7.9.2.1	available	57
		7.9.2.2	onOff	57
7.10	FC2Co	nfig Struc	t Reference	58
	7.10.1	Detailed	Description	58
	7.10.2	Construc	tor & Destructor Documentation	58
		7.10.2.1	FC2Config	58
	7.10.3	Property	Documentation	58
		7.10.3.1	asyncBusSpeed	58
		7.10.3.2	bandwidthAllocation	59

vi CONTENTS

7.10.3.3 grabMode	59
7.10.3.4 grabTimeout	59
7.10.3.5 isochBusSpeed	59
7.10.3.6 numBuffers	59
7.10.3.7 numImageNotifications	59
7.11 FC2Exception Class Reference	60
7.11.1 Detailed Description	60
7.11.2 Constructor & Destructor Documentation	61
7.11.2.1 FC2Exception	61
7.11.2.2 FC2Exception	61
7.11.2.3 FC2Exception	61
7.11.2.4 ~FC2Exception	61
7.11.2.5 FC2Exception	61
7.11.2.6 FC2Exception	61
7.11.3 Property Documentation	61
7.11.3.1 CauseType	61
7.11.3.2 Type	61
7.12 FC2Version Struct Reference	62
7.12.1 Detailed Description	62
7.12.2 Property Documentation	62
7.12.2.1 build	62
7.12.2.2 major	62
7.12.2.3 minor	62
7.12.2.4 type	62
7.13 Format7ImageSettings Struct Reference	63
7.13.1 Detailed Description	63
7.13.2 Property Documentation	63
7.13.2.1 height	63
7.13.2.2 mode	63
7.13.2.3 offsetX	63
7.13.2.4 offsetY	63
7.13.2.5 pixelFormat	64
7.13.2.6 width	64
7.14 Format7Info Struct Reference	65
7.14.1 Detailed Description	65
7.14.2 Property Documentation	66

CONTENTS vii

	7.14.2.1	imageHStepSize			 	 	 . 66
	7.14.2.2	$image VS tep Size \ . \ .$. 66
	7.14.2.3	maxHeight			 	 	 . 66
	7.14.2.4	maxPacketSize			 	 	 . 66
	7.14.2.5	maxWidth			 	 	 . 66
	7.14.2.6	minPacketSize			 	 	 . 66
	7.14.2.7	mode			 	 	 . 66
	7.14.2.8	offsetHStepSize			 	 	 . 66
	7.14.2.9	$off set VS tep Size \ . \ .$. 66
	7.14.2.10	packetSize			 	 	 . 66
	7.14.2.11	percentage			 	 	 . 66
	7.14.2.12	pixel Format Bit Field			 	 	 . 67
7.15 Format	7PacketIn	fo Struct Reference .			 	 	 . 68
7.15.1	Detailed 1	Description			 	 	 . 68
7.15.2	Property	Documentation			 	 	 . 68
	7.15.2.1	maxBytesPerPacket			 	 	 . 68
	7.15.2.2	recommendedBytesI	PerPacke	t	 	 	 . 68
	7.15.2.3	unitBytesPerPacket			 	 	 . 68
7.16 GigECo	onfig Struc	et Reference			 	 	 . 69
7.16.1	Detailed 1	Description			 	 	 . 69
7.16.2	Property	Documentation			 	 	 . 69
	7.16.2.1	channels			 	 	 . 69
	7.16.2.2	numChannels			 	 	 . 69
7.17 GigEIm	nageSettin	gs Struct Reference .			 	 	 . 70
7.17.1	Detailed 1	Description			 	 	 . 70
7.17.2	Property	Documentation			 	 	 . 70
	7.17.2.1	height			 	 	 . 70
	7.17.2.2	offset $X \dots \dots$. 70
	7.17.2.3	offsetY			 	 	 . 70
	7.17.2.4	pixelFormat			 	 	 . 70
	7.17.2.5	width			 	 	 . 70
7.18 GigEIm	nageSettin	gsInfo Struct Referen	ce		 	 	 . 71
7.18.1	Detailed 1	Description			 	 	 . 71
7.18.2	Property	Documentation			 	 	 . 71
	7.18.2.1	imageHStepSize			 	 	 . 71
	7.18.2.2	$image VS tep Size \ . \ .$. 71

viii CONTENTS

	7.18.2.3	maxHeight	71
	7.18.2.4	maxWidth	72
	7.18.2.5	offsetHStepSize	72
	7.18.2.6	offsetVStepSize	72
	7.18.2.7	pixelFormatBitField	72
7.19 GigEP	roperty St	ruct Reference	73
7.19.1	Detailed	Description	73
7.19.2	Property	Documentation	73
	7.19.2.1	isReadable	73
	7.19.2.2	isWritable	73
	7.19.2.3	max	73
	7.19.2.4	min	73
	7.19.2.5	propType	74
	7.19.2.6	value	74
7.20 GigES	treamChai	nnel Struct Reference	75
7.20.1	Detailed	Description	75
7.20.2	Property	Documentation	75
	7.20.2.1	destinationIpAddress	75
	7.20.2.2	doNotFragment	75
	7.20.2.3	hostPost	75
	7.20.2.4	interPacketDelay	76
	7.20.2.5	networkInterfaceIndex	76
	7.20.2.6	packetSize	76
	7.20.2.7	sourcePort	76
7.21 Image	Metadata S	Struct Reference	77
7.21.1	Detailed	Description	77
7.21.2	Property	Documentation	77
	7.21.2.1	embeddedBrightness	77
	7.21.2.2	embeddedExposure	78
	7.21.2.3	embeddedFrameCounter	78
	7.21.2.4	embeddedGain	78
	7.21.2.5	embeddedGPIOPinState	78
	7.21.2.6	embeddedROIPosition	78
	7.21.2.7	embeddedShutter	78
	7.21.2.8	embeddedStrobePattern	78
	7.21.2.9	embeddedTimeStamp	78

7.21.2.10 embeddedWhiteBalance	78
7.22 JpegOption Struct Reference	79
7.22.1 Detailed Description	79
7.22.2 Constructor & Destructor Documentation	79
7.22.2.1 JpegOption	79
7.22.3 Property Documentation	79
7.22.3.1 progressive	79
7.22.3.2 quality	79
7.23 Jpg2Option Struct Reference	80
7.23.1 Detailed Description	80
7.23.2 Constructor & Destructor Documentation	80
7.23.2.1 Jpg2Option	80
7.23.3 Property Documentation	80
7.23.3.1 quality	80
7.24 LutData Struct Reference	81
7.24.1 Detailed Description	81
7.24.2 Property Documentation	81
7.24.2.1 enabled	81
7.24.2.2 inputBitDepth	81
7.24.2.3 numBanks	81
7.24.2.4 numChannels	82
7.24.2.5 numEntries	82
7.24.2.6 outputBitDepth	82
7.24.2.7 supported	82
7.25 ManagedAVIRecorder Class Reference	83
7.25.1 Detailed Description	83
7.25.2 Constructor & Destructor Documentation	83
7.25.2.1 ManagedAVIRecorder	83
7.25.2.2 ~ManagedAVIRecorder	83
7.25.3 Member Function Documentation	83
7.25.3.1 AVIAppend	83
7.25.3.2 AVIClose	83
7.25.3.3 AVIOpen	84
7.26 ManagedBusManager Class Reference	85
7.26.1 Detailed Description	86
7.26.2 Constructor & Destructor Documentation	87

	7.26.2.1 ManagedBusManager	87
	7.26.2.2 ~ManagedBusManager	87
	7.26.2.3 !ManagedBusManager	87
7.26.3	Member Function Documentation	87
	7.26.3.1 ConvertToManagedGuid	87
	7.26.3.2 ConvertToNativeGuid	87
	7.26.3.3 DiscoverGigECameras	87
	7.26.3.4 FireBusReset	87
	7.26.3.5 ForceIPAddressToCamera	88
	7.26.3.6 GetCameraFromIndex	88
	7.26.3.7 GetCameraFromIPAddress	88
	7.26.3.8 GetCameraFromSerialNumber	88
	7.26.3.9 GetCameraSerialNumberFromIndex	89
	7.26.3.10 GetDeviceFromIndex	89
	7.26.3.11 GetInterfaceTypeFromGuid	89
	7.26.3.12 GetNumOfCameras	90
	7.26.3.13 GetNumOfDevices	90
	7.26.3.14 ReadPhyRegister	90
	7.26.3.15 RegisterCallback	90
	7.26.3.16 RescanBus	91
	7.26.3.17 UnregisterCallback	91
	7.26.3.18 WritePhyRegister	91
7.27 Mana	gedCamera Class Reference	92
7.27.1	Detailed Description	93
7.27.2	Constructor & Destructor Documentation	94
	7.27.2.1 ManagedCamera	94
	7.27.2.2 ~ManagedCamera	94
	7.27.2.3 !ManagedCamera	94
7.27.3	Member Function Documentation	94
	7.27.3.1 GetFormat7Configuration	94
	7.27.3.2 GetFormat7Info	94
	7.27.3.3 GetVideoModeAndFrameRate	95
	7.27.3.4 GetVideoModeAndFrameRateInfo	95
	7.27.3.5 SetFormat7Configuration	95
	7.27.3.6 SetFormat7Configuration	96
	7.27.3.7 SetVideoModeAndFrameRate	96

		7.27.3.8	ValidateFormat7Settings	96
7.28	Manag	edCameral	Base Class Reference	97
	7.28.1	Detailed l	Description	00
	7.28.2	Construct	tor & Destructor Documentation	01
		7.28.2.1	ManagedCameraBase	01
		7.28.2.2	\sim Managed Camera Base	01
	7.28.3	Member 1	Function Documentation	01
		7.28.3.1	Connect	01
		7.28.3.2	Disconnect	01
		7.28.3.3	EnableLUT	01
		7.28.3.4	FireSoftwareTrigger	01
		7.28.3.5	GetActiveLUTBank	02
		7.28.3.6	GetCameraInfo	02
		7.28.3.7	GetConfiguration	02
		7.28.3.8	GetEmbeddedImageInfo	02
		7.28.3.9	GetGPIOPinDirection	02
		7.28.3.10	GetLUTBankInfo	03
		7.28.3.11	GetLUTChannel	03
		7.28.3.12	GetLUTInfo	03
		7.28.3.13	GetMemoryChannel	04
		7.28.3.14	GetMemoryChannelInfo	04
		7.28.3.15	GetNativeCamera	04
		7.28.3.16	GetProperty	04
		7.28.3.17	GetPropertyInfo	05
		7.28.3.18	GetStrobe	05
		7.28.3.19	GetStrobeInfo	05
		7.28.3.20	GetTriggerMode	06
		7.28.3.21	GetTriggerModeInfo	06
		7.28.3.22	IsConnected	06
		7.28.3.23	OnNativeCallback	06
		7.28.3.24	ReadRegister	06
		7.28.3.25	ReadRegisterBlock	07
		7.28.3.26	RestoreFromMemoryChannel	07
		7.28.3.27	RetrieveBuffer	07
		7.28.3.28	SaveToMemoryChannel	80
		7.28.3.29	SetActiveLUTBank	08

xii CONTENTS

		7.28.3.30	SetCallback
		7.28.3.31	SetConfiguration
		7.28.3.32	SetEmbeddedImageInfo
		7.28.3.33	SetGPIOPinDirection
		7.28.3.34	SetGPIOPinDirection
		7.28.3.35	SetLUTChannel
		7.28.3.36	SetProperty
		7.28.3.37	SetProperty
		7.28.3.38	SetStrobe 110
		7.28.3.39	SetTriggerMode
		7.28.3.40	StartCapture
		7.28.3.41	StartCapture
		7.28.3.42	StopCapture
		7.28.3.43	WaitForBufferEvent
		7.28.3.44	WriteRegister
		7.28.3.45	WriteRegister
		7.28.3.46	WriteRegisterBlock
7	7.28.4	Member	Data Documentation
		7.28.4.1	m_externalDelegate
		7.28.4.2	m_internalDelegate
		7.28.4.3	m_pNativeCamBase
7.29 N	Manage	edGigECa	mera Class Reference
7	7.29.1	Detailed	Description
7	7.29.2	Construc	tor & Destructor Documentation
		7.29.2.1	ManagedGigECamera
		7.29.2.2	~ManagedGigECamera
		7.29.2.3	!ManagedGigECamera
7	7.29.3	Member	Function Documentation
		7.29.3.1	DiscoverGigEPacketSize
		7.29.3.2	GetGigEImageBinningSettings
		7.29.3.3	GetGigEImageSettings
		7.29.3.4	GetGigEImageSettingsInfo
		7.29.3.5	GetGigEImagingMode
		7.29.3.6	GetGigEProperty
		7.29.3.7	GetGigEStreamChannelInfo
		7.29.3.8	GetNumStreamChannels

CONTENTS xiii

	7.29.3.9	QueryGigEImagingMode	. 118
	7.29.3.10	ReadGVCPMemory	. 119
	7.29.3.11	ReadGVCPRegister	. 119
	7.29.3.12	ReadGVCPRegisterBlock	. 119
	7.29.3.13	SetGigEImageBinningSettings	. 119
	7.29.3.14	SetGigEImageSettings	. 119
	7.29.3.15	SetGigEImagingMode	. 120
	7.29.3.16	SetGigEProperty	. 120
	7.29.3.17	SetGigEStreamChannelInfo	. 120
	7.29.3.18	WriteGVCPMemory	. 120
	7.29.3.19	WriteGVCPRegister	. 120
	7.29.3.20	WriteGVCPRegister	. 121
	7.29.3.21	WriteGVCPRegisterBlock	. 121
7.30 Manag	edImage C	Class Reference	. 122
7.30.1	Detailed ?	Description	. 124
7.30.2	Construct	tor & Destructor Documentation	. 125
	7.30.2.1	ManagedImage	. 125
	7.30.2.2	ManagedImage	. 125
	7.30.2.3	ManagedImage	. 125
	7.30.2.4	ManagedImage	. 125
	7.30.2.5	ManagedImage	. 125
	7.30.2.6	ManagedImage	. 125
	7.30.2.7	ManagedImage	. 125
	7.30.2.8	~ManagedImage	. 125
	7.30.2.9	ManagedImage	. 125
	7.30.2.10	!ManagedImage	. 125
7.30.3	Member 1	Function Documentation	. 125
	7.30.3.1	CalculateStatistics	. 125
	7.30.3.2	Convert	. 125
	7.30.3.3	Convert	. 125
	7.30.3.4	DetermineBitsPerPixel	. 126
	7.30.3.5	GetNativeImage	. 126
	7.30.3.6	GetRawNativeImagePointer	. 126
	7.30.3.7	IsNativeImageValid	. 126
	7.30.3.8	ReleaseBuffer	. 126
	7.30.3.9	Save	. 126

	7.30.3.10 Save	26
	7.30.3.11 Save	27
	7.30.3.12 Save	27
	7.30.3.13 Save	27
	7.30.3.14 Save	27
	7.30.3.15 Save	27
	7.30.3.16 Save	28
	7.30.3.17 SetData	28
	7.30.3.18 SetDimensions	28
7.30.4	Property Documentation	28
	7.30.4.1 bayerTileFormat	28
	7.30.4.2 bitmap	28
	7.30.4.3 bitsPerPixel	28
	7.30.4.4 colorProcessingAlgorithm	29
	7.30.4.5 cols	29
	7.30.4.6 data	29
	7.30.4.7 defaultColorProcessingAlgorithm	29
	7.30.4.8 defaultOutputPixelFormat	29
	7.30.4.9 imageMetadata	29
	7.30.4.10 pixelFormat	29
	7.30.4.11 rows	29
	7.30.4.12 stride	29
	7.30.4.13 timeStamp	29
7.31 Manag	edImageStatistics Class Reference	30
7.31.1	Constructor & Destructor Documentation	31
	7.31.1.1 ManagedImageStatistics	31
	7.31.1.2 ~ManagedImageStatistics	31
7.31.2	Member Function Documentation	31
	7.31.2.1 DisableAll	31
	7.31.2.2 EnableAll	31
	7.31.2.3 EnableGreyOnly	31
	7.31.2.4 EnableHSLOnly	31
	7.31.2.5 EnableRGBOnly	31
	7.31.2.6 GetChannelStatus	31
	7.31.2.7 GetHistogram	31
	7.31.2.8 GetMean	31

7.31.2.9	9 GetNativeImageStatistics	31
7.31.2.1	10 GetNumPixelValues	31
7.31.2.1	11 GetPixelValueRange	31
7.31.2.1	12 GetRange	31
7.31.2.1	13 GetStatistics	31
7.31.2.1	14 SetChannelStatus	31
7.32 ManagedPGRC	Guid Class Reference	32
7.32.1 Detaile	d Description	32
7.32.2 Constru	uctor & Destructor Documentation	32
7.32.2.1	1 ManagedPGRGuid	32
7.32.2.2	2 ManagedPGRGuid	33
7.32.2.3	3 ManagedPGRGuid	33
7.32.3 Membe	er Function Documentation	33
7.32.3.1	1 Equals	33
	2 GetHashCode	
	3 operator!=	
	4 operator=	
	5 operator==	
	er Data Documentation	
	1 value0	
	2 value1	
	3 value2	
	4 value3	
_	es Class Reference	
7.33.1 Membe	er Function Documentation	34
	1 LaunchBrowser	
7.33.1.2	2 LaunchCommand	34
	3 LaunchHelp	
7.33.2 Propert	ry Documentation	
7.33.2.1	· · · · · · · · · · · · · · · · · · ·	
	2 systemInfo	
	uct Reference	
	d Description	
	actor & Destructor Documentation	
	1 PgmOption	
7.34.3 Propert	y Documentation	35

7.34.3.1 binaryFile
7.35 PngOption Struct Reference
7.35.1 Detailed Description
7.35.2 Constructor & Destructor Documentation
7.35.2.1 PngOption
7.35.3 Property Documentation
7.35.3.1 compressionLevel
7.35.3.2 interlaced
7.36 PpmOption Struct Reference
7.36.1 Detailed Description
7.36.2 Constructor & Destructor Documentation
7.36.2.1 PpmOption
7.36.3 Property Documentation
7.36.3.1 binaryFile
7.37 StrobeControl Struct Reference
7.37.1 Detailed Description
7.37.2 Property Documentation
7.37.2.1 delay
7.37.2.2 duration
7.37.2.3 onOff
7.37.2.4 polarity
7.37.2.5 source
7.38 StrobeInfo Struct Reference
7.38.1 Detailed Description
7.38.2 Property Documentation
7.38.2.1 maxValue
7.38.2.2 minValue
7.38.2.3 onOffSupported
7.38.2.4 polaritySupported
7.38.2.5 present
7.38.2.6 readOutSupported
7.38.2.7 source
7.39 SystemInfo Struct Reference
7.39.1 Detailed Description
7.39.2 Property Documentation
7.39.2.1 byteOrder

CONTENTS xvii

	7.39.2.2	cpuDescription			 	 	 	142
	7.39.2.3	driverList			 	 	 	142
	7.39.2.4	gpuDescription	ı . .		 	 	 	142
	7.39.2.5	libraryList			 	 	 	142
	7.39.2.6	numCpuCores			 	 	 	142
	7.39.2.7	osDescription			 	 	 	142
	7.39.2.8	osType			 	 	 	142
	7.39.2.9	screenHeight .			 	 	 	142
	7.39.2.10	screenWidth .			 	 	 	142
	7.39.2.11	systemMemory	Size		 	 	 	142
7.40 TiffOp	tion Struct	Reference			 	 	 	143
7.40.1	Detailed	Description			 	 	 	143
7.40.2	Member	Enumeration Do	cumentatio	on	 	 	 	143
	7.40.2.1	CompressionM	lethod		 	 	 	143
7.40.3	Construc	tor & Destructor	Documen	tation .	 	 	 	144
	7.40.3.1	TiffOption			 	 	 	144
7.40.4	Property	Documentation			 	 	 	144
	7.40.4.1	compression .			 	 	 	144
7.41 TimeSt	tamp Struc	t Reference			 	 	 	145
7.41.1	Detailed	Description			 	 	 	145
7.41.2	Property	Documentation			 	 	 	145
	7.41.2.1	cycleCount			 	 	 	145
	7.41.2.2	cycleOffset			 	 	 	145
	7.41.2.3	cycleSeconds			 	 	 	145
	7.41.2.4	microSeconds			 	 	 	145
	7.41.2.5	seconds			 	 	 	145
7.42 Transla	ate Class R	eference			 	 	 	146
7.42.1	Member	Function Docum	nentation .		 	 	 	149
	7.42.1.1	ToMgd			 	 	 	149
	7.42.1.2	ToMgd			 	 	 	149
	7.42.1.3	ToMgd			 	 	 	149
	7.42.1.4	ToMgd			 	 	 	149
	7.42.1.5	ToMgd			 	 	 	149
	7.42.1.6	ToMgd			 	 	 	149
	7.42.1.7	ToMgd			 	 	 	149
	7.42.1.8	ToMgd			 	 	 	149

xviii CONTENTS

7.42.1.9 ToMgd
7.42.1.10 ToMgd
7.42.1.11 ToMgd
7.42.1.12 ToMgd
7.42.1.13 ToMgd
7.42.1.14 ToMgd
7.42.1.15 ToMgd
7.42.1.16 ToMgd
7.42.1.17 ToMgd
7.42.1.18 ToMgd
7.42.1.19 ToMgd
7.42.1.20 ToMgd
7.42.1.21 ToMgd
7.42.1.22 ToMgd
7.42.1.23 ToMgd
7.42.1.24 ToMgd
7.42.1.25 ToMgd
7.42.1.26 ToMgd
7.42.1.27 ToMgd
7.42.1.28 ToMgd
7.42.1.29 ToMgd
7.42.1.30 ToMgd
7.42.1.31 ToMgd
7.42.1.32 ToNative
7.42.1.33 ToNative
7.42.1.34 ToNative
7.42.1.35 ToNative
7.42.1.36 ToNative
7.42.1.37 ToNative
7.42.1.38 ToNative
7.42.1.39 ToNative
7.42.1.40 ToNative
7.42.1.41 ToNative
7.42.1.42 ToNative
7.42.1.43 ToNative
7.42.1.44 ToNative

CONTENTS xix

7.42.1.45 ToNative	 	 	 	 		 			. .		149
7.42.1.46 ToNative	 	 	 	 		 			. .		149
7.42.1.47 ToNative	 	 	 	 		 			. .		149
7.42.1.48 ToNative	 	 	 	 	 	 					149
7.42.1.49 ToNative	 	 	 		 	 					149
7.42.1.50 ToNative	 	 	 		 	 					149
7.42.1.51 ToNative	 	 	 	 	 	 			. .		149
7.42.1.52 ToNative	 	 	 		 	 					149
7.42.1.53 ToNative	 	 	 		 	 					149
7.42.1.54 ToNative	 	 	 	 	 	 			. .		149
7.42.1.55 ToNative	 	 	 		 	 					149
7.42.1.56 ToNative	 	 	 	 	 	 			. .		149
7.42.1.57 ToNative	 	 	 	 	 	 			. .		149
7.42.1.58 ToNative	 	 	 	 	 	 			. .		149
7.42.1.59 ToNative	 	 	 		 	 					149
7.42.1.60 ToNative	 	 	 	 	 	 					149
7.42.1.61 ToNative	 	 	 	 	 	 					149
7.42.1.62 translate	 	 	 	 	 	 					149
7.42.1.63 translate	 	 	 	 	 	 					149
7.42.1.64 translate	 	 	 	 	 	 					149
7.42.1.65 translate	 	 	 		 	 					149
7.42.1.66 translate	 	 	 	 	 	 					149
7.42.1.67 translate	 	 	 	 	 	 					149
7.42.1.68 translate	 	 	 	 		 			. .		149
7.42.1.69 translate	 	 	 		 	 					149
7.42.1.70 translate	 	 	 	 	 	 					149
7.42.1.71 translate	 	 	 	 	 	 					149
7.42.1.72 translate	 	 	 	 	 	 			. .		149
7.42.1.73 translate	 	 	 		 	 					149
7.42.1.74 translate	 	 	 	 	 	 			. .		149
7.42.1.75 translate	 	 	 	 	 	 			. .		149
7.42.1.76 translate	 	 	 			 					149
7.42.1.77 translate	 	 	 			 					149
7.42.1.78 translate	 	 	 		 	 					149
7.42.1.79 translate	 	 	 			 					149
7.42.1.80 translate	 	 	 	 	 	 			. .		149

		7.42.1.81	translate				 	 	 	 		 	149
		7.42.1.82	translate				 	 	 	 		 	149
		7.42.1.83	translate				 	 	 	 		 	149
		7.42.1.84	translate				 	 	 	 		 	149
		7.42.1.85	translate				 	 	 	 		 	149
		7.42.1.86	translate				 	 	 	 		 	149
		7.42.1.87	translate				 	 	 	 		 	149
		7.42.1.88	translate				 	 	 	 		 	149
		7.42.1.89	translate				 	 	 	 		 	149
		7.42.1.90	translate				 	 	 	 		 	149
		7.42.1.91	translate				 	 	 	 		 	149
		7.42.1.92	translate				 	 	 	 		 	149
		7.42.1.93	translate				 	 	 	 		 	149
		7.42.1.94	translate				 	 	 	 		 	149
		7.42.1.95	translate				 	 	 	 		 	149
		7.42.1.96	translate				 	 	 	 		 	149
		7.42.1.97	translate				 	 	 	 		 	149
7.43	Trigger	rMode Stru	ıct Referei	ice			 	 	 	 		 	150
	7.43.1	Detailed 1	Descriptio	n			 	 	 	 		 	150
	7.43.2	Property	Document	ation			 	 	 	 		 	150
		7.43.2.1	mode				 	 	 	 		 	150
		7.43.2.2	onOff				 	 	 	 		 	150
		7.43.2.3	paramete	r			 	 	 	 		 	150
		7.43.2.4	polarity .				 	 	 	 		 	150
		7.43.2.5	source .				 	 	 	 		 	150
7.44	Trigger	rModeInfo	Struct Re	ference .			 	 	 	 		 	151
	7.44.1	Detailed 1	Descriptio	n			 	 	 	 		 	151
	7.44.2	Property	Document	ation			 	 	 	 		 	151
		7.44.2.1	modeMas	sk			 	 	 	 		 	151
		7.44.2.2	onOffSup	ported .			 	 	 	 		 	151
		7.44.2.3	polarityS	upported			 	 	 	 		 	151
		7.44.2.4	present .				 	 	 	 		 	151
		7.44.2.5	readOutS	upported			 	 	 	 		 	152
		7.44.2.6	software	ſriggerSu	ıppoı	rted	 	 	 	 		 	152
		7.44.2.7	sourceMa	ask			 	 	 	 		 	152
		7.44.2.8	valueRea	dable			 	 	 	 		 	152

Chapter 1

Module Index

1.1 Modules

Here	is	a	list	of	all	modules:
------	----	---	------	----	-----	----------

Enumerations	. 9
Structures	
Image saving structures	. 27

2 Module Index

Chapter 2

Namespace Index

2.1	Namespace 1	List
-----	-------------	------

ere is a list of all namespaces with brief descriptions:	
FlyCapture2	29
FlyCapture2Managed	30
FlyCapture2Managed::Gui	40

4 Namespace Index

Chapter 3

Class Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

6 Class Index

Option
Option
Option
beControl
beInfo
emInfo
Option
eStamp
nslate
gerMode
gerModeInfo

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

AviOption (Options for saving AVI files)
CameraControlDialog (CameraControlDialog: managed wrapper of FlyCap-
ture2::CameraControlDialog (see for details))
CameraInfo (Camera information)
CameraProperty (A specific camera property)
CameraPropertyInfo (Information about a specific camera property)
CameraSelectionDialog (CameraControlDialog: managed wrapper of FlyCap-
ture2::CameraSelectionDialog (see for details))
ConfigROM (Camera configuration ROM)
EmbeddedImageInfo (Properties of the possible embedded image information)
EmbeddedImageInfoProperty (Properties of a single embedded image info property)
FC2Config (Configuration for a camera)
FC2Exception (Exception that is thrown when an error is encountered)
FC2Version (The current version of the library)
Format7ImageSettings (Format 7 image settings)
Format7Info (Format 7 information for a single mode)
Format7PacketInfo (Format 7 packet information)
GigEConfig (Configuration for a GigE camera)
GigEImageSettings (Image settings for a GigE camera)
GigEImageSettingsInfo (Format 7 information for a single mode)
GigEProperty (A GigE property)
GigEStreamChannel (Information about a single GigE stream channel)
ImageMetadata (Metadata related to an image)
JpegOption (Options for saving JPEG image)
Jpg2Option (Options for saving JPEG2000 image)
LutData (Information about the camera's look up table)
ManagedAVIRecorder (ManagedAVIRecorder provides the functionality for the user to record
images to an AVI file)
ManagedBusManager (ManagedBusManager provides the functionality for the user to get an
PGRGuid for a desired camera or device easily)
ManagedCamera (ManagedCamera represents a physical camera that uses the IIDC register set)
ManagedCameraBase (Abstract base class that represents a generic camera that defines a general
interface to a camera)

8 Class Index

ManagedGigECamera (The GigECamera object represents a physical Gigabit Ethernet camera)	114
ManagedImage (The ManagedImageImage class is used to retrieve images from a camera, con-	
vert between multiple pixel formats and save images to disk)	122
ManagedImageStatistics	130
ManagedPGRGuid (Managed version of a PGRGuid)	132
ManagedUtilities	134
PgmOption (Options for saving PGM images)	135
PngOption (Options for saving PNG images)	136
PpmOption (Options for saving PPM images)	137
StrobeControl (A camera strobe)	138
StrobeInfo (A camera strobe property)	139
SystemInfo (Description of the system)	141
TiffOption (Options for saving TIFF images)	143
TimeStamp (Timestamp information)	145
Translate	146
TriggerMode (A camera trigger)	150
TriggerModeInfo (Information about a camera trigger property)	151

Chapter 5

Module Documentation

5.1 Enumerations

Enumerations

```
• enum ErrorType {
```

Undefined = -1,

Ok,

Failed,

NotImplemented,

FailedBusMasterConnection,

NotConnected,

InitFailed,

NotInitialized,

InvalidParameter,

InvalidSettings,

InvalidBuManager,

Memory Allocation Failed,

LowLevelFailure,

NotFound,

FailedGuid,

InvalidPacketSize,

InvalidMode,

NotInFormat7,

NotSupported,

Timeout,

BusMasterFailed,

InvalidGeneration,

LutFailed,

IidcFailed,

10 Module Documentation

```
StrobeFailed,
  TriggerFailed,
  PropertyFailed,
  PropertyNotPresent,
  RegisterFailed,
  ReadRegisterFailed,
  WriteRegisterFailed,
  IsochFailed,
  IsochAlreadyStarted,
  IsochNotStarted,
  IsochStartFailed,
  IsochRetrieveBufferFailed,
  IsochStopFailed,
  IsochSyncFailed,
  IsochBandwidthExceeded,
  ImageConversionFailed,
  ImageLibraryFailure,
  BufferTooSmall,
  ImageConsistencyError }
     The error types returned by functions.
• enum ManagedCallbackType {
  BusReset,
  Arrival.
  Removal }
     The type of bus callback to register a callback function for.
• enum GrabMode {
  DropFrames,
  BufferFrames,
  Unspecified = -2 }
     The grab strategy employed during image transfer.
• enum GrabTimeout {
  None = 0,
  Infinite = -1,
  Unspecified = -2 }
     Timeout options for grabbing images.
• enum BandwidthAllocation {
  Off = 0,
  On = 1,
  Unsupported = 2,
  Unspecified = -2 }
```

5.1 Enumerations

Bandwidth allocation options for 1394 devices.

```
• enum InterfaceType {
 Ieee1394,
  Usb2,
 GigE,
 Unknown = -1 }
     Interfaces that a camera may use to communicate with a host.
• enum PropertyType {
  Brightness,
  AutoExposure,
 Sharpness,
  WhiteBalance,
 Hue,
  Saturation,
  Gamma,
 Iris,
 Focus,
 Zoom,
 Pan,
 Tilt,
 Shutter,
 Gain,
 TriggerMode,
 TriggerDelay,
 FrameRate,
 Temperature,
  Unspecified = -2 }
     Camera properties.
• enum FrameRate {
 FrameRate1_875,
 FrameRate3_75,
 FrameRate7_5,
 FrameRate15,
 FrameRate30,
 FrameRate60,
 FrameRate120,
 FrameRate240,
 FrameRateFormat7,
  NumberOfFrameRates }
```

12 Module Documentation

Frame rates in frames per second.

```
• enum VideoMode {
  VideoMode160x120Yuv444,
  VideoMode320x240Yuv422,
  VideoMode640x480Yuv411,
  VideoMode640x480Yuv422,
  VideoMode640x480Rgb,
  VideoMode640x480Y8,
  VideoMode640x480Y16,
  VideoMode800x600Yuv422,
  VideoMode800x600Rgb,
  VideoMode800x600Y8,
  VideoMode800x600Y16,
  VideoMode1024x768Yuv422,
  VideoMode1024x768Rgb,
  VideoMode1024x768Y8,
  VideoMode1024x768Y16,
  VideoMode1280x960Yuv422,
  VideoMode1280x960Rgb,
  VideoMode1280x960Y8,
  VideoMode1280x960Y16,
  VideoMode1600x1200Yuv422,
  VideoMode1600x1200Rgb,
  VideoMode1600x1200Y8,
  VideoMode1600x1200Y16,
  VideoModeFormat7,
 NumberOfVideoModes }
    DCAM video modes.
• enum Mode {
  Mode0 = 0,
 Mode1,
 Mode2,
  Mode3.
  Mode4,
  Mode5.
  Mode6,
  Mode7,
  Mode8,
  Mode9,
```

Mode10,

5.1 Enumerations 13

```
Mode11,
  Mode12,
  Mode13,
  Mode14,
  Mode15,
  Mode16,
  Mode17,
  Mode18,
  Mode19,
  Mode20,
  Mode21,
  Mode22,
  Mode23,
  Mode24,
  Mode25,
  Mode26,
  Mode27,
  Mode28,
  Mode29,
  Mode30,
  Mode31,
  NumberOfModes }
     Camera modes for DCAM formats as well as Format7.
• enum PixelFormat {
 PixelFormatMono8 = 0x800000000,
 PixelFormat411Yuv8 = 0x40000000,
 PixelFormat422Yuv8 = 0x20000000,
 PixelFormat444Yuv8 = 0x10000000,
 PixelFormatRgb8 = 0x080000000,
 PixelFormatMono16 = 0x04000000,
 PixelFormatRgb16 = 0x020000000,
 PixelFormatSignedMono16 = 0x01000000,
 PixelFormatSignedRgb16 = 0x00800000,
 PixelFormatRaw8 = 0x00400000,
 PixelFormatRaw16 = 0x002000000,
 PixelFormatMono12 = 0x00100000,
 PixelFormatRaw12 = 0x00080000,
 PixelFormatBgr = 0x80000008,
  PixelFormatBgru = 0x40000008,
 PixelFormatRgb = PixelFormatRgb8,
 PixelFormatRgbu = 0x40000002,
  NumberOfPixelFormats = 15 }
```

Pixel formats available for Format7 modes.

```
• enum BusSpeed {
  S100,
  S200,
 S400,
  S480,
  S800,
 S1600,
 S3200,
 GigE_10Base_T,
 GigE_100Base_T,
 GigE_1000Base_T,
 GigE_10000Base_T,
 Fastest,
  Any,
 Unknown = -1 }
     Bus speeds.
• enum ColorProcessingAlgorithm {
  Default,
  NoColorProcessing,
 NearestNeighbor,
 EdgeSensing,
 HQLinear,
 Rigorous }
     Color processing algorithms.
• enum BayerTileFormat {
  None = 0,
 RGGB,
 GRBG,
 GBRG,
 BGGR }
     Bayer tile formats.
• enum ImageFileFormat {
 From File Extension = -1,
 Pgm,
 Ppm,
 Bmp,
 Jpeg,
 Jpeg2000,
```

15 **5.1 Enumerations**

```
Tiff,
  Png,
  Raw }
     File formats to be used for saving images to disk.
• enum StatisticsChannel {
  Grey,
  Red,
  Green,
  Blue.
  Hue,
  Saturation,
  Lightness,
  NumberOfStatisticsChannels }
     Channels that allow statistics to be calculated.
• enum OSType {
  WindowsX86,
  WindowsX64,
  LinuxX86,
  LinuxX64,
  Mac,
  UnknownOS }
     Possible operating systems.
• enum ByteOrder {
  LittleEndian,
  BigEndian }
     Possible byte orders.
• enum GigEPropertyType {
  Heartbeat,
  HeartbearTimeout,
  PacketSize,
  PacketDelay }
     Possible properties that can be queried from the camera.
```

Enumeration Type Documentation

enum BandwidthAllocation 5.1.1.1

5.1.1

Bandwidth allocation options for 1394 devices.

Enumerator:

Off Do not allocate bandwidth.

On Allocate bandwidth.

This is the default setting.

Unsupported Bandwidth allocation is not supported by either the camera or operating system.

Unspecified Unspecified grab mode.

Unspecified property type.

Not specified.

Unspecified timeout setting.

This leaves the current setting unchanged.

5.1.1.2 enum BayerTileFormat

Bayer tile formats.

Enumerator:

None Non-blocking wait.

No bayer tile format.

RGGB Red-Green-Blue.

GRBG Green-Red-Blue-Green.

GBRG Green-Blue-Red-Green.

BGGR Blue-Green-Green-Red.

5.1.1.3 enum BusSpeed

Bus speeds.

Enumerator:

S100 100Mbits/sec.

S200 200Mbits/sec.

S400 400Mbits/sec.

S480 480Mbits/sec.

Only for USB cameras.

\$800 800Mbits/sec.

S1600 1600Mbits/sec.

S3200 3200Mbits/sec.

GigE_10Base_T

 $GigE_100Base_T$

GigE_1000Base_T

GigE_10000Base_T

Fastest The fastest speed available.

Any Any speed that is available.

Unknown Unknown interface.

Unknown bus speed.

5.1 Enumerations 17

5.1.1.4 enum ByteOrder

Possible byte orders.

Enumerator:

LittleEndian BigEndian

5.1.1.5 enum ColorProcessingAlgorithm

Color processing algorithms.

Please refer to our knowledge base at article at http://www.ptgrey.com/support/kb/index.asp?a=4&q=33 for complete details for each algorithm.

Enumerator:

Default Default method.

NoColorProcessing No color processing.

NearestNeighbor Fastest but lowest quality.

Equivalent to FLYCAPTURE_NEAREST_NEIGHBOR_FAST in FlyCapture.

Edge Sensing Weights surrounding pixels based on localized edge orientation.

HQLinear Similar quality to rigorous but much faster.

Rigorous Slowest but produces the best results.

5.1.1.6 enum ErrorType

The error types returned by functions.

Enumerator:

Undefined Undefined.

Ok Function returned with no errors.

Failed General failure.

NotImplemented Function has not been implemented.

FailedBusMasterConnection Could not connect to Bus Master.

NotConnected Camera has not been connected.

InitFailed Initialization failed.

NotInitialized Camera has not been initialized.

InvalidParameter Invalid parameter passed to function.

InvalidSettings Setting set to camera is invalid.

InvalidBuManager Invalid Bus Manager object.

MemoryAllocationFailed Could not allocate memory.

LowLevelFailure Low level error.

NotFound Device not found.

FailedGuid GUID failure.

InvalidPacketSize Packet size set to camera is invalid.

InvalidMode Invalid mode has been passed to function.

NotInFormat7 Error due to not being in Format7.

NotSupported This feature is unsupported.

Timeout Timeout error.

BusMasterFailed Bus Master Failure.

InvalidGeneration Generation Count Mismatch.

LutFailed Look Up Table failure.

IidcFailed IIDC failure.

StrobeFailed Strobe failure.

TriggerFailed Trigger failure.

PropertyFailed Property failure.

PropertyNotPresent Property is not present.

RegisterFailed Register access failed.

ReadRegisterFailed Register read failed.

WriteRegisterFailed Register write failed.

IsochFailed Isochronous failure.

IsochAlreadyStarted Isochronous transfer has already been started.

IsochNotStarted Isochronous transfer has not been started.

IsochStartFailed Isochronous start failed.

IsochRetrieveBufferFailed Isochronous retrieve buffer failed.

IsochStopFailed Isochronous stop failed.

IsochSyncFailed Isochronous image synchronization failed.

IsochBandwidthExceeded Isochronous bandwidth exceeded.

ImageConversionFailed Image conversion failed.

ImageLibraryFailure Image library failure.

BufferTooSmall Buffer is too small.

ImageConsistencyError There is an image consistency error.

5.1.1.7 enum FrameRate

Frame rates in frames per second.

Enumerator:

FrameRate1_875 1.875 fps.

FrameRate3_75 3.75 fps.

FrameRate7_5 7.5 fps.

FrameRate15 15 fps.

FrameRate30 30 fps.

FrameRate60 60 fps.

FrameRate120 120 fps.

FrameRate240 240 fps.

FrameRateFormat7 Custom frame rate for Format7 functionality.

NumberOfFrameRates Number of possible camera frame rates.

5.1 Enumerations 19

5.1.1.8 enum GigEPropertyType

Possible properties that can be queried from the camera.

Enumerator:

Heartbeat
HeartbearTimeout
PacketSize
PacketDelay

5.1.1.9 enum GrabMode

The grab strategy employed during image transfer.

This type controls how images that stream off the camera accumulate in a user buffer for handling. Unlike earlier versions of the FlyCapture SDK, it is no longer necessary to explicitly start the image grabbing process before specifying an image grabbing mode.

Enumerator:

DropFrames Grabs the newest image in the user buffer each time the RetrieveBuffer() function is called.

Older images are dropped instead of accumulating in the user buffer. Grabbing blocks if the camera has not finished transmitting the next available image. If the camera is transmitting images faster than the application can grab them, images may be dropped and only the most recent image is stored for grabbing. Note that this mode is the equivalent of flycaptureLockLatest in earlier versions of the FlyCapture SDK.

BufferFrames Images accumulate in the user buffer, and the oldest image is grabbed for handling before being discarded.

This member can be used to guarantee that each image is seen. However, image processing time must not exceed transmission time from the camera to the buffer. Grabbing blocks if the camera has not finished transmitting the next available image. The buffer size is controlled by the numBuffers parameter in the FC2Config struct. Note that this mode is the equivalent of flycaptureLockNext in earlier versions of the FlyCapture SDK.

Unspecified Unspecified grab mode.

Unspecified property type.

Not specified.

Unspecified timeout setting.

This leaves the current setting unchanged.

5.1.1.10 enum GrabTimeout

Timeout options for grabbing images.

Enumerator:

None Non-blocking wait. No bayer tile format.

Infinite Wait indefinitely.

Unspecified Unspecified grab mode.

Unspecified property type.

Not specified.

Unspecified timeout setting.

This leaves the current setting unchanged.

5.1.1.11 enum ImageFileFormat

File formats to be used for saving images to disk.

Enumerator:

```
FromFileExtension Determine file format from file extension.
```

Pgm Portable gray map.

Ppm Portable pixmap.

Bmp Bitmap.

Jpeg JPEG.

Jpeg2000 JPEG 2000.

Tiff Tagged image file format.

Png Portable network graphics.

Raw Raw data.

5.1.1.12 enum InterfaceType

Interfaces that a camera may use to communicate with a host.

Enumerator:

```
Ieee1394 IEEE-1394 (Includes 1394a and 1394b).
```

Usb2 USB 2.0.

GigE GigE.

Unknown Unknown interface.

Unknown bus speed.

5.1.1.13 enum ManagedCallbackType

The type of bus callback to register a callback function for.

Enumerator:

BusReset Register for all bus events.

Arrival Register for arrivals only.

Removal Register for removals only.

5.1 Enumerations 21

5.1.1.14 enum Mode

Camera modes for DCAM formats as well as Format7.

Enumerator:

Mode0

Mode1

Mode2

Mode3

Mode4

Mode5

Mode6

Mode7

Mode8

Mode9

Mode10

Mode11

Mode12

Mode13

Mode14

Mode15

Mode16

Mode17

Mode18

Mode19

Mode20

Mode21

Mode22

Mode23

Mode24

Mode25

Mode26

Mode27

Mode28

Mode29

Mode30

Mode31

NumberOfModes

5.1.1.15 enum OSType

Possible operating systems.

Enumerator:

Windows X86 All Windows 32-bit variants.

Windows X64 All Windows 64-bit variants.

LinuxX86 All Linux 32-bit variants.

LinuxX64 All Linux 32-bit variants.

Mac Mac OSX.

UnknownOS Unknown operating system.

5.1.1.16 enum PixelFormat

Pixel formats available for Format7 modes.

Enumerator:

PixelFormatMono8 8 bits of mono information.

PixelFormat411Yuv8 YUV 4:1:1.

PixelFormat422Yuv8 YUV 4:2:2.

PixelFormat444Yuv8 YUV 4:4:4.

PixelFormatRgb8 R = G = B = 8 bits.

PixelFormatMono16 16 bits of mono information.

PixelFormatRgb16 R = G = B = 16 bits.

PixelFormatSignedMono16 16 bits of signed mono information.

PixelFormatSignedRgb16 R = G = B = 16 bits signed.

PixelFormatRaw8 8 bit raw data output of sensor.

PixelFormatRaw16 16 bit raw data output of sensor.

PixelFormatMono12 12 bits of mono information.

PixelFormatRaw12 12 bit raw data output of sensor.

PixelFormatBgr 24 bit BGR.

PixelFormatBgru 32 bit BGRU.

PixelFormatRgb 24 bit RGB.

PixelFormatRgbu 32 bit RGBU.

NumberOfPixelFormats Number of pixel formats.

5.1.1.17 enum PropertyType

Camera properties.

Not all properties may be supported, depending on the camera model.

Enumerator:

Brightness Brightness.

5.1 Enumerations 23

AutoExposure Auto exposure.

Sharpness Sharpness.

WhiteBalance White balance.

Hue Hue.

Saturation Saturation.

Gamma Gamma.

Iris Iris.

Focus Focus.

Zoom Zoom.

Pan Pan.

Tilt Tilt.

Shutter Shutter.

Gain Gain.

TriggerMode Trigger mode.

TriggerDelay Trigger delay.

FrameRate Frame rate.

Temperature Temperature.

Unspecified Unspecified grab mode.

Unspecified property type.

Not specified.

Unspecified timeout setting.

This leaves the current setting unchanged.

5.1.1.18 enum StatisticsChannel

Channels that allow statistics to be calculated.

Enumerator:

Grey

Red

Green

Blue

Hue Hue.

Saturation Saturation.

Lightness

Number Of Statistics Channels

5.1.1.19 enum VideoMode

DCAM video modes.

Enumerator:

VideoMode160x120Yuv444 160x120 YUV444.

VideoMode320x240Yuv422 320x240 YUV422.

VideoMode640x480Yuv411 640x480 YUV411.

VideoMode640x480Yuv422 640x480 YUV422.

VideoMode640x480Rgb 640x480 24-bit RGB.

VideoMode640x480Y8 640x480 8-bit.

VideoMode640x480Y16 640x480 16-bit.

VideoMode800x600Yuv422 800x600 YUV422.

VideoMode800x600Rgb 800x600 RGB.

VideoMode800x600Y8 800x600 8-bit.

VideoMode800x600Y16 800x600 16-bit.

VideoMode1024x768Yuv422 1024x768 YUV422.

VideoMode1024x768Rgb 1024x768 RGB.

VideoMode1024x768Y8 1024x768 8-bit.

VideoMode1024x768Y16 1024x768 16-bit.

VideoMode1280x960Yuv422 1280x960 YUV422.

VideoMode1280x960Rgb 1280x960 RGB.

VideoMode1280x960Y8 1280x960 8-bit.

VideoMode1280x960Y16 1280x960 16-bit.

VideoMode1600x1200Yuv422 1600x1200 YUV422.

VideoMode1600x1200Rgb 1600x1200 RGB.

VideoMode1600x1200Y8 1600x1200 8-bit.

VideoMode1600x1200Y16 1600x1200 16-bit.

VideoModeFormat7 Custom video mode for Format7 functionality.

NumberOfVideoModes Number of possible video modes.

5.2 Structures 25

5.2 Structures

Collaboration diagram for Structures:



Classes

• struct FC2Version

The current version of the library.

• struct GigEProperty

A GigE property.

• struct GigEStreamChannel

Information about a single GigE stream channel.

• struct GigEConfig

Configuration for a GigE camera.

• struct GigEImageSettingsInfo

Format 7 information for a single mode.

• struct GigEImageSettings

Image settings for a GigE camera.

• struct FC2Config

Configuration for a camera.

• struct CameraPropertyInfo

Information about a specific camera property.

• struct CameraProperty

A specific camera property.

• struct TriggerModeInfo

Information about a camera trigger property.

• struct TriggerMode

A camera trigger.

• struct StrobeInfo

A camera strobe property.

struct StrobeControl

A camera strobe.

• struct Format7ImageSettings

Format 7 image settings.

• struct Format7Info

Format 7 information for a single mode.

• struct Format7PacketInfo

Format 7 packet information.

• struct TimeStamp

Timestamp information.

• struct ConfigROM

 ${\it Camera\ configuration\ ROM}.$

• struct CameraInfo

Camera information.

• struct EmbeddedImageInfoProperty

Properties of a single embedded image info property.

• struct EmbeddedImageInfo

Properties of the possible embedded image information.

• struct ImageMetadata

Metadata related to an image.

• struct LutData

Information about the camera's look up table.

• struct PngOption

Options for saving PNG images.

Modules

• Image saving structures.

 ${\it These structures define various parameters used for saving images.}$

5.3 Image saving structures.

These structures define various parameters used for saving images.

Collaboration diagram for Image saving structures.:



Classes

• struct PngOption

Options for saving PNG images.

• struct PpmOption

Options for saving PPM images.

• struct PgmOption

Options for saving PGM images.

• struct TiffOption

Options for saving TIFF images.

• struct JpegOption

Options for saving JPEG image.

• struct Jpg2Option

Options for saving JPEG2000 image.

• struct AviOption

Options for saving AVI files.

• struct SystemInfo

Description of the system.

5.3.1 Detailed Description

These structures define various parameters used for saving images.

Chapter 6

Namespace Documentation

6.1 FlyCapture2 Namespace Reference

6.2 FlyCapture2Managed Namespace Reference

Namespaces

• namespace Gui

Classes

• class FC2Exception

Exception that is thrown when an error is encountered.

• class ManagedAVIRecorder

ManagedAVIRecorder provides the functionality for the user to record images to an AVI file.

• class ManagedBusManager

ManagedBusManager provides the functionality for the user to get an PGRGuid for a desired camera or device easily.

• class ManagedCamera

ManagedCamera represents a physical camera that uses the IIDC register set.

• class ManagedCameraBase

Abstract base class that represents a generic camera that defines a general interface to a camera.

• struct FC2Version

The current version of the library.

• struct GigEProperty

 $A\ GigE\ property.$

• struct GigEStreamChannel

Information about a single GigE stream channel.

• struct GigEConfig

Configuration for a GigE camera.

• struct GigEImageSettingsInfo

Format 7 information for a single mode.

• struct GigEImageSettings

Image settings for a GigE camera.

• struct FC2Config

 $Configuration\ for\ a\ camera.$

• struct CameraPropertyInfo

Information about a specific camera property.

• struct CameraProperty

A specific camera property.

• struct TriggerModeInfo

Information about a camera trigger property.

• struct TriggerMode

A camera trigger.

• struct StrobeInfo

A camera strobe property.

struct StrobeControl

A camera strobe.

• struct Format7ImageSettings

Format 7 image settings.

• struct Format7Info

Format 7 information for a single mode.

• struct Format7PacketInfo

Format 7 packet information.

• struct TimeStamp

Timestamp information.

• struct ConfigROM

Camera configuration ROM.

• struct CameraInfo

Camera information.

• struct EmbeddedImageInfoProperty

Properties of a single embedded image info property.

• struct EmbeddedImageInfo

Properties of the possible embedded image information.

• struct ImageMetadata

Metadata related to an image.

• struct LutData

Information about the camera's look up table.

• struct PngOption

Options for saving PNG images.

• struct PpmOption

Options for saving PPM images.

• struct PgmOption

Options for saving PGM images.

• struct TiffOption

Options for saving TIFF images.

• struct JpegOption

Options for saving JPEG image.

• struct Jpg2Option

Options for saving JPEG2000 image.

• struct AviOption

Options for saving AVI files.

• struct SystemInfo

Description of the system.

• class ManagedGigECamera

The GigECamera object represents a physical Gigabit Ethernet camera.

• class ManagedImage

The ManagedImageImage class is used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

- class ManagedImageStatistics
- class ManagedPGRGuid

Managed version of a PGRGuid.

- class ManagedUtilities
- class Translate

Enumerations

```
• enum ErrorType {
```

Undefined = -1,

Ok,

Failed,

NotImplemented,

FailedBusMasterConnection,

NotConnected,

InitFailed,

NotInitialized,

InvalidParameter,

InvalidSettings,

InvalidBuManager,

Memory Allocation Failed,

```
LowLevelFailure,
  NotFound,
 FailedGuid,
 InvalidPacketSize,
 InvalidMode,
  NotInFormat7,
  NotSupported,
 Timeout,
  BusMasterFailed,
 InvalidGeneration,
 LutFailed,
 IidcFailed,
  StrobeFailed.
 TriggerFailed,
  PropertyFailed,
  PropertyNotPresent,
 RegisterFailed,
  ReadRegisterFailed,
  WriteRegisterFailed,
 IsochFailed,
  IsochAlreadyStarted,
 IsochNotStarted,
 IsochStartFailed,
 IsochRetrieveBufferFailed,
 IsochStopFailed,
 IsochSyncFailed,
 IsochBandwidthExceeded,
 ImageConversionFailed,
 ImageLibraryFailure,
  BufferTooSmall,
 ImageConsistencyError }
     The error types returned by functions.
• enum ManagedCallbackType {
  BusReset,
  Arrival,
 Removal }
     The type of bus callback to register a callback function for.
• enum GrabMode {
 DropFrames,
 BufferFrames,
  Unspecified = -2 }
```

The grab strategy employed during image transfer.

```
• enum GrabTimeout {
  None = 0,
  Infinite = -1,
  Unspecified = -2 }
     Timeout options for grabbing images.
• enum BandwidthAllocation {
  Off = 0,
  On = 1,
  Unsupported = 2,
  Unspecified = -2 }
     Bandwidth allocation options for 1394 devices.
• enum InterfaceType {
  Ieee1394,
  Usb2,
  GigE,
  Unknown = -1 }
     Interfaces that a camera may use to communicate with a host.
• enum PropertyType {
  Brightness,
  AutoExposure,
  Sharpness,
  WhiteBalance,
  Hue,
  Saturation,
  Gamma,
  Iris,
  Focus,
  Zoom,
  Pan,
  Tilt,
  Shutter,
  Gain,
  TriggerMode,
  TriggerDelay,
  FrameRate,
  Temperature,
  Unspecified = -2 }
     Camera properties.
```

```
• enum FrameRate {
 FrameRate1_875,
 FrameRate3_75,
 FrameRate7_5,
 FrameRate15.
 FrameRate30,
 FrameRate60.
 FrameRate120,
 FrameRate240,
 FrameRateFormat7,
  NumberOfFrameRates }
    Frame rates in frames per second.
• enum VideoMode {
  VideoMode160x120Yuv444,
  VideoMode320x240Yuv422,
  VideoMode640x480Yuv411,
  VideoMode640x480Yuv422,
  VideoMode640x480Rgb,
  VideoMode640x480Y8,
  VideoMode640x480Y16,
  VideoMode800x600Yuv422,
  VideoMode800x600Rgb,
  VideoMode800x600Y8,
  VideoMode800x600Y16.
  VideoMode1024x768Yuv422,
  VideoMode1024x768Rgb,
  VideoMode1024x768Y8,
  VideoMode1024x768Y16,
  VideoMode1280x960Yuv422,
  VideoMode1280x960Rgb,
  VideoMode1280x960Y8,
  VideoMode1280x960Y16,
  VideoMode1600x1200Yuv422,
  VideoMode1600x1200Rgb,
  VideoMode1600x1200Y8,
  VideoMode1600x1200Y16,
  VideoModeFormat7,
 NumberOfVideoModes }
```

DCAM video modes.

```
• enum Mode {
 Mode0 = 0,
 Mode1,
  Mode2,
 Mode3,
 Mode4,
 Mode5,
  Mode6,
 Mode7,
 Mode8,
  Mode9,
  Mode10,
  Mode11,
  Mode12,
  Mode13,
  Mode14,
 Mode15,
  Mode16,
  Mode17,
  Mode18,
  Mode19,
  Mode20,
  Mode21,
 Mode22,
  Mode23,
  Mode24,
  Mode25,
 Mode26,
  Mode27,
  Mode28,
  Mode29,
 Mode30,
 Mode31,
  NumberOfModes }
     Camera modes for DCAM formats as well as Format7.
• enum PixelFormat {
 PixelFormatMono8 = 0x800000000,
 PixelFormat411Yuv8 = 0x40000000,
 PixelFormat422Yuv8 = 0x200000000,
 PixelFormat444Yuv8 = 0x100000000,
```

```
PixelFormatRgb8 = 0x080000000,
 PixelFormatMono16 = 0x04000000,
 PixelFormatRgb16 = 0x02000000,
 PixelFormatSignedMono16 = 0x01000000,
 PixelFormatSignedRgb16 = 0x00800000,
 PixelFormatRaw8 = 0x00400000,
 PixelFormatRaw16 = 0x00200000,
 PixelFormatMono12 = 0x00100000,
 PixelFormatRaw12 = 0x00080000,
 PixelFormatBgr = 0x80000008,
 PixelFormatBgru = 0x40000008,
 PixelFormatRgb = PixelFormatRgb8,
 PixelFormatRgbu = 0x40000002,
  NumberOfPixelFormats = 15 }
     Pixel formats available for Format7 modes.
• enum BusSpeed {
  S100,
 S200,
  S400,
  S480,
  S800,
 S1600,
 S3200,
 GigE_10Base_T,
 GigE_100Base_T,
 GigE_1000Base_T,
 GigE_10000Base_T,
 Fastest,
  Any,
  Unknown = -1
     Bus speeds.
• enum ColorProcessingAlgorithm {
 Default,
 NoColorProcessing,
 NearestNeighbor,
 EdgeSensing,
 HQLinear,
 Rigorous }
     Color processing algorithms.
```

```
• enum BayerTileFormat {
  None = 0,
 RGGB,
 GRBG,
 GBRG,
 BGGR }
     Bayer tile formats.
• enum ImageFileFormat {
 From File Extension = -1,
 Pgm,
 Ppm,
 Bmp,
 Jpeg,
 Jpeg2000,
 Tiff,
 Png,
 Raw }
     File formats to be used for saving images to disk.
• enum StatisticsChannel {
  Grey,
 Red,
 Green,
 Blue,
 Hue,
 Saturation,
 Lightness,
  NumberOfStatisticsChannels }
     Channels that allow statistics to be calculated.
• enum OSType {
  WindowsX86,
  WindowsX64,
 LinuxX86,
 LinuxX64,
  Mac,
 UnknownOS }
     Possible operating systems.
• enum ByteOrder {
 LittleEndian,
 BigEndian }
```

Possible byte orders.

```
    enum GigEPropertyType {
        Heartbeat,
        HeartbearTimeout,
        PacketSize,
        PacketDelay }
        Possible properties that can be queried from the camera.
```

Functions

- public delegate void EnumCallback (System::IntPtr parameter, unsigned int serialNumber)

 Bus event callback function prototype.
- public delegate void ImageEventCallback (ManagedImage^ image)

 The external callback that will be used by managed consumers.
- protected delegate void ImageCallbackDelegate (FlyCapture2::Image *image, void *data)

 Internal callback that we use internally so we can create the proper proper external callback for users.

6.2.1 Function Documentation

6.2.1.1 public delegate void FlyCapture2Managed::EnumCallback (System::IntPtr parameter, unsigned int serialNumber)

Bus event callback function prototype.

Defines the syntax of the callback function that is passed into RegisterCallback() and UnregisterCallback().

6.2.1.2 protected delegate void FlyCapture2Managed::ImageCallbackDelegate (FlyCapture2::Image * image, void * data)

Internal callback that we use internally so we can create the proper proper external callback for users.

6.2.1.3 public delegate void FlyCapture2Managed::ImageEventCallback (ManagedImage^ image)

The external callback that will be used by managed consumers.

6.3 FlyCapture2Managed::Gui Namespace Reference

Classes

- class CameraControlDialog

 CameraControlDialog: managed wrapper of FlyCapture2::CameraControlDialog (see for details).
- class CameraSelectionDialog

 CameraControlDialog: managed wrapper of FlyCapture2::CameraSelectionDialog (see for details).

Chapter 7

Class Documentation

7.1 AviOption Struct Reference

Options for saving AVI files.

Public Member Functions

• AviOption ()

Properties

• float frameRate

Frame rate of the stream.

7.1.1 Detailed Description

Options for saving AVI files.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 AviOption() [inline]

7.1.3 Property Documentation

7.1.3.1 float frameRate

Frame rate of the stream.

42 Class Documentation

7.2 CameraControlDialog Class Reference

CameraControlDialog: managed wrapper of FlyCapture2::CameraControlDialog (see for details).

Public Member Functions

- CameraControlDialog ()
- ~CameraControlDialog ()
- void Connect (ManagedCamera^{\(\Lambda\)} camera)
- void Disconnect ()
- void Show ()
- void Hide ()
- bool IsVisible ()

7.2.1 Detailed Description

CameraControlDialog: managed wrapper of FlyCapture2::CameraControlDialog (see for details).

7.2.2 Constructor & Destructor Documentation

- 7.2.2.1 CameraControlDialog ()
- **7.2.2.2** ∼CameraControlDialog ()
- 7.2.3 Member Function Documentation
- 7.2.3.1 void Connect (FlyCapture2Managed::ManagedCamera[^] camera)
- 7.2.3.2 void Disconnect ()
- 7.2.3.3 void Hide ()
- 7.2.3.4 bool IsVisible ()
- **7.2.3.5 void Show** ()

7.3 CameraInfo Struct Reference

Camera information.

Properties

• unsigned int serialNumber

Device serial number.

• InterfaceType interfaceType

Interface type.

• bool isColorCamera

Flag indicating if this is a color camera.

• System::String^ modelName

Device model name.

• System::String^ vendorName

Device vendor name.

• System::String^ sensorInfo

String detailing the sensor information.

 $\bullet \; System::String^{\wedge} \; sensorResolution$

String providing the sensor resolution.

• System::String^ driverName

Driver name of driver being used.

• System::String[^] firmwareVersion

Firmware version of camera.

• System::String^ firmwareBuildTime

Firmware build time.

• BusSpeed maximumBusSpeed

Maximum bus speed.

• BayerTileFormat bayerTileFormat

Bayer tile format.

IIDC specific information

• unsigned int iidcVersion *DCAM version*.

• ConfigROM configROM

Configuration ROM data.

44 Class Documentation

GigE specific information

• unsigned int gigEMajorVersion GigE Vision version.

• unsigned int gigEMinorVersion GigE Vision minor version.

• System::String^ userDefinedName

User defined name.

• System::String^ xmlURL1 XML URL 1.

• System::String[^] xmIURL2 XML URL 2.

- System::Net::NetworkInformation::PhysicalAddress ^ macAddress MAC address.
- System::Net::IPAddress[∧] ipAddress

 IP address.
- System::Net::IPAddress^ subnetMask Subnet mask.
- System::Net::IPAddress[^] defaultGateway
 Default gateway.

7.3.1 Detailed Description

Camera information.

7.3.2 Property Documentation

7.3.2.1 BayerTileFormat bayerTileFormat

Bayer tile format.

7.3.2.2 ConfigROM configROM

Configuration ROM data.

7.3.2.3 System:: Net:: IPAddress^ defaultGateway

Default gateway.

7.3.2.4 System:: String^{\(\)} driverName

Driver name of driver being used.

7.3.2.5 System:: String[^] firmwareBuildTime

Firmware build time.

7.3.2.6 System:: String^ firmwareVersion

Firmware version of camera.

7.3.2.7 unsigned int gigEMajorVersion

GigE Vision version.

7.3.2.8 unsigned int gigEMinorVersion

GigE Vision minor version.

7.3.2.9 unsigned int iidcVersion

DCAM version.

7.3.2.10 InterfaceType interfaceType

Interface type.

7.3.2.11 System:: Net:: IPAddress^ ipAddress

IP address.

7.3.2.12 bool isColorCamera

Flag indicating if this is a color camera.

7.3.2.13 System:: Net:: NetworkInformation:: PhysicalAddress^ macAddress

MAC address.

7.3.2.14 BusSpeed maximumBusSpeed

Maximum bus speed.

46 Class Documentation

7.3.2.15 System:: String^ modelName

Device model name.

7.3.2.16 System:: String sensorInfo

String detailing the sensor information.

7.3.2.17 System:: String^ sensorResolution

String providing the sensor resolution.

7.3.2.18 unsigned int serialNumber

Device serial number.

7.3.2.19 System:: Net:: IPAddress^ subnetMask

Subnet mask.

7.3.2.20 System:: String^ userDefinedName

User defined name.

7.3.2.21 System:: String^ vendorName

Device vendor name.

7.3.2.22 System:: String^ xmlURL1

XML URL 1.

7.3.2.23 System:: String^ xmlURL2

XML URL 2.

7.4 CameraProperty Struct Reference

A specific camera property.

Public Member Functions

- CameraProperty ()
- CameraProperty (PropertyType type)

Properties

• PropertyType type

Property info type.

• bool present

Flag indicating if the property is present.

• bool absControl

Flag controlling absolute mode.

• bool onePush

Flag controlling one push.

• bool onOff

Flag controlling on/off.

• bool autoManualMode

Flag controlling auto.

• unsigned int valueA

Value A (integer).

• unsigned int valueB

Value B (integer).

• float absValue

Floating point value.

7.4.1 Detailed Description

A specific camera property.

48 Class Documentation

7.4.2 Constructor & Destructor Documentation

7.4.2.1 CameraProperty () [inline]

7.4.2.2 CameraProperty (PropertyType *type*) [inline]

7.4.3 Property Documentation

7.4.3.1 bool absControl

Flag controlling absolute mode.

7.4.3.2 float absValue

Floating point value.

7.4.3.3 bool autoManualMode

Flag controlling auto.

7.4.3.4 bool onePush

Flag controlling one push.

7.4.3.5 bool on Off

Flag controlling on/off.

7.4.3.6 bool present

Flag indicating if the property is present.

7.4.3.7 PropertyType type

Property info type.

7.4.3.8 unsigned int valueA

Value A (integer).

7.4.3.9 unsigned int valueB

Value B (integer).

Applies only to the white balance red value. Use Value A for the blue value.

7.5 CameraPropertyInfo Struct Reference

Information about a specific camera property.

Public Member Functions

- CameraPropertyInfo ()
- CameraPropertyInfo (PropertyType type)

Properties

• PropertyType type

Property info type.

• bool present

Flag indicating if the property is present.

• bool autoSupported

Flag indicating if auto is supported.

• bool manualSupported

Flag indicating if manual is supported.

• bool onOffSupported

Flag indicating if on/off is supported.

• bool onePushSupported

Flag indicating if one push is supported.

• bool absValSupported

Flag indicating if absolute mode is supported.

• bool readOutSupported

Flag indicating if property value can be read out.

• unsigned int min

Minimum value (as an integer).

• unsigned int max

Maximum value (as an integer).

• float absMin

Minimum value (as a floating point value).

• float absMax

Maximum value (as a floating point value).

• System::String^ units

Textual description of units.

• System::String^ unitAbbr

Abbreviated textual description of units.

7.5.1 Detailed Description

Information about a specific camera property.

This structure is also also used as the TriggerDelayInfo structure.

7.5.2 Constructor & Destructor Documentation

7.5.2.1 CameraPropertyInfo() [inline]

7.5.2.2 CameraPropertyInfo (PropertyType type) [inline]

7.5.3 Property Documentation

7.5.3.1 float absMax

Maximum value (as a floating point value).

7.5.3.2 float absMin

Minimum value (as a floating point value).

7.5.3.3 bool absValSupported

Flag indicating if absolute mode is supported.

7.5.3.4 bool autoSupported

Flag indicating if auto is supported.

7.5.3.5 bool manual Supported

Flag indicating if manual is supported.

7.5.3.6 unsigned int max

Maximum value (as an integer).

7.5.3.7 unsigned int min

Minimum value (as an integer).

7.5.3.8 bool onePushSupported

Flag indicating if one push is supported.

7.5.3.9 bool on Off Supported

Flag indicating if on/off is supported.

7.5.3.10 bool present

Flag indicating if the property is present.

7.5.3.11 bool readOutSupported

Flag indicating if property value can be read out.

7.5.3.12 PropertyType type

Property info type.

7.5.3.13 System:: String^ unitAbbr

Abbreviated textual description of units.

7.5.3.14 System:: String^{\(\chi\)} units

Textual description of units.

7.6 CameraSelectionDialog Class Reference

CameraControlDialog: managed wrapper of FlyCapture2::CameraSelectionDialog (see for details).

Public Member Functions

- CameraSelectionDialog ()
- ~CameraSelectionDialog ()
- bool ShowModal ()

Show the CameraSelectionDlg.

• array< ManagedPGRGuid[^] > ^ GetSelectedCameraGuids ()

Returns the list of camera guids selected by the user while in ShowModal().

7.6.1 Detailed Description

CameraControlDialog: managed wrapper of FlyCapture2::CameraSelectionDialog (see for details).

7.6.2 Constructor & Destructor Documentation

7.6.2.1 CameraSelectionDialog()

7.6.2.2 ~CameraSelectionDialog ()

7.6.3 Member Function Documentation

7.6.3.1 array< ManagedPGRGuid^ > GetSelectedCameraGuids ()

Returns the list of camera guids selected by the user while in ShowModal().

Returns:

Array of PGRGuids identifying the selected cameras.

7.6.3.2 bool ShowModal ()

Show the CameraSelectionDlg.

Returns:

Whether Ok (true) or Cancel (false) was clicked.

7.7 ConfigROM Struct Reference

Camera configuration ROM.

Properties

- unsigned int node Vendor Id Vendor ID of a node.
- unsigned int chipIdHi

 Chip ID (high part).
- unsigned int chipIdLo *Chip ID (low part).*
- unsigned int unitSpecId

 Unit Spec ID, usually 0xa02d.
- unsigned int unitSWVer

 Unit software version.
- unsigned int unitSubSWVer Unit sub software version.
- unsigned int vendorUniqueInfo0 Vendor unique info 0.
- unsigned int vendorUniqueInfo1 Vendor unique info 1.
- unsigned int vendorUniqueInfo2 Vendor unique info 2.
- unsigned int vendorUniqueInfo3 Vendor unique info 3.
- System::String[^] keyword Keyword.

7.7.1 Detailed Description

Camera configuration ROM.

7.7.2 Property Documentation

7.7.2.1 unsigned int chipIdHi

Chip ID (high part).

7.7.2.2 unsigned int chipIdLo

Chip ID (low part).

7.7.2.3 System:: String^{\(\)} keyword

Keyword.

7.7.2.4 unsigned int nodeVendorId

Vendor ID of a node.

7.7.2.5 unsigned int unitSpecId

Unit Spec ID, usually 0xa02d.

7.7.2.6 unsigned int unitSubSWVer

Unit sub software version.

7.7.2.7 unsigned int unitSWVer

Unit software version.

7.7.2.8 unsigned int vendorUniqueInfo0

Vendor unique info 0.

7.7.2.9 unsigned int vendorUniqueInfo1

Vendor unique info 1.

7.7.2.10 unsigned int vendorUniqueInfo2

Vendor unique info 2.

7.7.2.11 unsigned int vendorUniqueInfo3

Vendor unique info 3.

7.8 EmbeddedImageInfo Struct Reference

Properties of the possible embedded image information.

Public Member Functions

• EmbeddedImageInfo ()

Properties

- EmbeddedImageInfoProperty[^] timestamp
- EmbeddedImageInfoProperty[^] gain
- EmbeddedImageInfoProperty^ shutter
- EmbeddedImageInfoProperty^ brightness
- EmbeddedImageInfoProperty^ exposure
- $\bullet \ EmbeddedImageInfoProperty ^{\wedge} \ whiteBalance$
- EmbeddedImageInfoProperty^ frameCounter
- EmbeddedImageInfoProperty^ strobePattern
- EmbeddedImageInfoProperty^ GPIOPinState
- EmbeddedImageInfoProperty^ ROIPosition

7.8.1 Detailed Description

Properties of the possible embedded image information.

782	Constructor	& Doctructor	Documentation
1.8.2	Constructor	& Destructor	Documentation

- **7.8.2.1 EmbeddedImageInfo()** [inline]
- **7.8.3** Property Documentation
- 7.8.3.1 EmbeddedImageInfoProperty^ brightness
- 7.8.3.2 EmbeddedImageInfoProperty^ exposure
- $\textbf{7.8.3.3} \quad \textbf{EmbeddedImageInfoProperty}^{\wedge} \ \textbf{frameCounter}$
- 7.8.3.4 EmbeddedImageInfoProperty^ gain
- 7.8.3.5 EmbeddedImageInfoProperty^ GPIOPinState
- 7.8.3.6 EmbeddedImageInfoProperty^ ROIPosition
- 7.8.3.7 EmbeddedImageInfoProperty^ shutter
- 7.8.3.8 EmbeddedImageInfoProperty^ strobePattern
- 7.8.3.9 EmbeddedImageInfoProperty^ timestamp
- 7.8.3.10 EmbeddedImageInfoProperty^ whiteBalance

7.9 EmbeddedImageInfoProperty Struct Reference

Properties of a single embedded image info property.

Properties

• bool available

Whether this property is available.

• bool onOff

Whether this property is on or off.

7.9.1 Detailed Description

Properties of a single embedded image info property.

7.9.2 Property Documentation

7.9.2.1 bool available

Whether this property is available.

7.9.2.2 bool onOff

Whether this property is on or off.

7.10 FC2Config Struct Reference

Configuration for a camera.

Public Member Functions

• FC2Config ()

Properties

• unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

• unsigned int numImageNotifications

This is the number of notifications per image that will be triggered.

int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

• GrabMode grabMode

Grab mode for the camera.

• BusSpeed isochBusSpeed

Isochronous bus speed.

• BusSpeed asyncBusSpeed

Asynchronous bus speed.

• BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

7.10.1 Detailed Description

Configuration for a camera.

These options are options that are generally should be set before starting isochronous transfer.

7.10.2 Constructor & Destructor Documentation

7.10.2.1 FC2Config() [inline]

7.10.3 Property Documentation

7.10.3.1 BusSpeed asyncBusSpeed

Asynchronous bus speed.

7.10.3.2 BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

7.10.3.3 GrabMode grabMode

Grab mode for the camera.

The default is DROP_FRAMES.

7.10.3.4 int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

7.10.3.5 BusSpeed isochBusSpeed

Isochronous bus speed.

7.10.3.6 unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

7.10.3.7 unsigned int numImageNotifications

This is the number of notifications per image that will be triggered.

The default case is 1 notification at the end of a image. Setting this parameter to 2 will result in notifications after the first packet and at the end of image. Setting this parameter to anything more then 2 will divide the notifications equally throughout the buffer. The maximum number of notifications possible is bufferSize/packetSize since notifications need to land on packet boundaries.

7.11 FC2Exception Class Reference

Exception that is thrown when an error is encountered.

Public Member Functions

- FC2Exception ()
- FC2Exception (String^ string)
- FC2Exception (String^ string, Exception^ exception)
- ~FC2Exception ()

Protected Member Functions

• FC2Exception (Runtime::Serialization::SerializationInfo^ serializationInfo, Runtime::Serialization::StreamingContext context)

Package Functions

• FC2Exception (FlyCapture2::Error error)

Properties

- ErrorType Type [get]
- ErrorType CauseType [get]

7.11.1 Detailed Description

Exception that is thrown when an error is encountered.

This is used instead of returning an Error object as used in the C++ interface.

7.11.2 Constructor & Destructor Documentation

- **7.11.2.1** FC2Exception ()
- 7.11.2.2 FC2Exception (String\(^\) string\)
- 7.11.2.3 FC2Exception (String\(^\) string, Exception\(^\) exception\(^\)
- **7.11.2.4** ∼**FC2Exception** ()
- 7.11.2.5 FC2Exception (Runtime::Serialization::SerializationInfo^ serializationInfo, Runtime::Serialization::StreamingContext context) [protected]
- **7.11.2.6 FC2Exception (FlyCapture2::Error** *error*) [package]
- 7.11.3 Property Documentation
- **7.11.3.1 ErrorType CauseType** [get]
- **7.11.3.2 ErrorType Type** [get]

7.12 FC2Version Struct Reference

The current version of the library.

Properties

- unsigned int major

 Major version number.
- unsigned int minor

 Minor version number.
- unsigned int type

 Type version number.
- unsigned int build

 Build version number.

7.12.1 Detailed Description

The current version of the library.

7.12.2 Property Documentation

7.12.2.1 unsigned int build

Build version number.

7.12.2.2 unsigned int major

Major version number.

7.12.2.3 unsigned int minor

Minor version number.

7.12.2.4 unsigned int type

Type version number.

7.13 Format7ImageSettings Struct Reference

Format 7 image settings.

Properties

• Mode mode

Format 7 mode.

 \bullet unsigned int offsetX

Horizontal image offset.

• unsigned int offsetY

Vertical image offset.

• unsigned int width

Width of image.

• unsigned int height

Height of image.

• PixelFormat pixelFormat

Pixel format of image.

7.13.1 Detailed Description

Format 7 image settings.

7.13.2 Property Documentation

7.13.2.1 unsigned int height

Height of image.

7.13.2.2 Mode mode

Format 7 mode.

7.13.2.3 unsigned int offsetX

Horizontal image offset.

7.13.2.4 unsigned int offsetY

Vertical image offset.

7.13.2.5 PixelFormat pixelFormat

Pixel format of image.

7.13.2.6 unsigned int width

Width of image.

7.14 Format7Info Struct Reference

Format 7 information for a single mode.

Properties

• Mode mode

Format 7 mode.

• unsigned int maxWidth

Maximum image width.

• unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

unsigned int offsetVStepSize
 Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

• unsigned int pixelFormatBitField Supported pixel formats in a bit field.

• unsigned int packetSize

Current packet size in bytes.

unsigned int minPacketSize
 Minimum packet size in bytes for current mode.

• unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

• float percentage

Current packet size as a percentage of maximum packet size.

7.14.1 Detailed Description

Format 7 information for a single mode.

7.14.2 Property Documentation

7.14.2.1 unsigned int imageHStepSize

Horizontal step size for the image.

7.14.2.2 unsigned int imageVStepSize

Vertical step size for the image.

7.14.2.3 unsigned int maxHeight

Maximum image height.

7.14.2.4 unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

7.14.2.5 unsigned int maxWidth

Maximum image width.

7.14.2.6 unsigned int minPacketSize

Minimum packet size in bytes for current mode.

7.14.2.7 Mode mode

Format 7 mode.

7.14.2.8 unsigned int offsetHStepSize

Horizontal step size for the offset.

7.14.2.9 unsigned int offsetVStepSize

Vertical step size for the offset.

7.14.2.10 unsigned int packetSize

Current packet size in bytes.

7.14.2.11 float percentage

Current packet size as a percentage of maximum packet size.

7.14.2.12 unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

7.15 Format7PacketInfo Struct Reference

Format 7 packet information.

Properties

- unsigned int recommendedBytesPerPacket Recommended bytes per packet.
- unsigned int maxBytesPerPacket

 Maximum bytes per packet.
- unsigned int unitBytesPerPacket

 Minimum bytes per packet.

7.15.1 Detailed Description

Format 7 packet information.

7.15.2 Property Documentation

7.15.2.1 unsigned int maxBytesPerPacket

Maximum bytes per packet.

7.15.2.2 unsigned int recommendedBytesPerPacket

Recommended bytes per packet.

7.15.2.3 unsigned int unitBytesPerPacket

Minimum bytes per packet.

7.16 GigEConfig Struct Reference

Configuration for a GigE camera.

Properties

• unsigned int numChannels

Number of stream channels.

• array < GigEStreamChannel^ >^ channels

Array of stream channel data.

7.16.1 Detailed Description

Configuration for a GigE camera.

These options are options that are generally should be set before starting isochronous transfer.

7.16.2 Property Documentation

7.16.2.1 array < GigEStreamChannel $^{\wedge}$ $>^{\wedge}$ channels

Array of stream channel data.

7.16.2.2 unsigned int numChannels

Number of stream channels.

Read only.

7.17 GigEImageSettings Struct Reference

Image settings for a GigE camera.

Properties

- unsigned int offsetX

 Horizontal image offset.
- unsigned int offsetY

 Vertical image offset.
- unsigned int width Width of image.
- unsigned int height *Height of image.*
- PixelFormat pixelFormat Pixel format of image.

7.17.1 Detailed Description

Image settings for a GigE camera.

7.17.2 Property Documentation

7.17.2.1 unsigned int height

Height of image.

7.17.2.2 unsigned int offsetX

Horizontal image offset.

7.17.2.3 unsigned int offsetY

Vertical image offset.

7.17.2.4 PixelFormat pixelFormat

Pixel format of image.

7.17.2.5 unsigned int width

Width of image.

7.18 GigEImageSettingsInfo Struct Reference

Format 7 information for a single mode.

Properties

- unsigned int maxWidth

 Maximum image width.
- unsigned int maxHeight
 Maximum image height.
- unsigned int offsetHStepSize

 Horizontal step size for the offset.
- unsigned int offsetVStepSize

 Vertical step size for the offset.
- unsigned int imageHStepSize
 Horizontal step size for the image.
- unsigned int imageVStepSize

 Vertical step size for the image.
- unsigned int pixelFormatBitField

 Supported pixel formats in a bit field.

7.18.1 Detailed Description

Format 7 information for a single mode.

7.18.2 Property Documentation

7.18.2.1 unsigned int imageHStepSize

Horizontal step size for the image.

7.18.2.2 unsigned int imageVStepSize

Vertical step size for the image.

7.18.2.3 unsigned int maxHeight

Maximum image height.

7.18.2.4 unsigned int maxWidth

Maximum image width.

7.18.2.5 unsigned int offsetHStepSize

Horizontal step size for the offset.

7.18.2.6 unsigned int offsetVStepSize

Vertical step size for the offset.

7.18.2.7 unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

7.19 GigEProperty Struct Reference

A GigE property.

Properties

• GigEPropertyType propType

The type of property.

• bool isReadable

Whether the property is readable.

• bool isWritable

Whether the property is writable.

• unsigned int min

Minimum value.

• unsigned int max

Maximum value.

• unsigned int value

Current value.

7.19.1 Detailed Description

A GigE property.

7.19.2 Property Documentation

7.19.2.1 bool is Readable

Whether the property is readable.

If this is false, then no other value in this structure is valid.

7.19.2.2 bool is Writable

Whether the property is writable.

7.19.2.3 unsigned int max

Maximum value.

7.19.2.4 unsigned int min

Minimum value.

7.19.2.5 GigEPropertyType propType

The type of property.

7.19.2.6 unsigned int value

Current value.

7.20 GigEStreamChannel Struct Reference

Information about a single GigE stream channel.

Properties

• unsigned int networkInterfaceIndex

Network interface index used (or to use).

• unsigned int hostPost

Host port on the PC where the camera will send the data stream.

• bool doNotFragment

Disable IP fragmentation of packets.

• unsigned int packetSize

Packet size, in bytes.

• unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

• System::Net::IPAddress[^] destinationIpAddress

Destination IP address.

• unsigned int sourcePort

Source UDP port of the stream channel.

7.20.1 Detailed Description

Information about a single GigE stream channel.

7.20.2 Property Documentation

7.20.2.1 System:: Net:: IPAddress[^] destinationIpAddress

Destination IP address.

It can be a multicast or unicast address.

7.20.2.2 bool doNotFragment

Disable IP fragmentation of packets.

7.20.2.3 unsigned int hostPost

Host port on the PC where the camera will send the data stream.

7.20.2.4 unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

7.20.2.5 unsigned int networkInterfaceIndex

Network interface index used (or to use).

7.20.2.6 unsigned int packetSize

Packet size, in bytes.

7.20.2.7 unsigned int sourcePort

Source UDP port of the stream channel.

Read only.

7.21 ImageMetadata Struct Reference

Metadata related to an image.

Properties

- unsigned int embeddedTimeStamp

 Embedded timestamp.
- unsigned int embeddedGain Embedded gain.
- unsigned int embeddedShutter

 Embedded shutter:
- unsigned int embeddedBrightness Embedded brightness.
- unsigned int embeddedExposure Embedded exposure.
- unsigned int embeddedWhiteBalance Embedded white balance.
- unsigned int embeddedFrameCounter Embedded frame counter.
- unsigned int embeddedStrobePattern

 Embedded strobe pattern.
- unsigned int embeddedGPIOPinState

 Embedded GPIO pin state.
- unsigned int embeddedROIPosition Embedded ROI position.

7.21.1 Detailed Description

Metadata related to an image.

7.21.2 Property Documentation

7.21.2.1 unsigned int embeddedBrightness

Embedded brightness.

7.21.2.2 unsigned int embeddedExposure

Embedded exposure.

7.21.2.3 unsigned int embeddedFrameCounter

Embedded frame counter.

7.21.2.4 unsigned int embeddedGain

Embedded gain.

7.21.2.5 unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

7.21.2.6 unsigned int embeddedROIPosition

Embedded ROI position.

7.21.2.7 unsigned int embeddedShutter

Embedded shutter.

7.21.2.8 unsigned int embeddedStrobePattern

Embedded strobe pattern.

7.21.2.9 unsigned int embeddedTimeStamp

Embedded timestamp.

7.21.2.10 unsigned int embeddedWhiteBalance

Embedded white balance.

7.22 JpegOption Struct Reference

Options for saving JPEG image.

Public Member Functions

• JpegOption ()

Properties

• bool progressive

Whether to save as a progressive JPEG file.

• unsigned int quality

JPEG image quality in range (0-100).

7.22.1 Detailed Description

Options for saving JPEG image.

7.22.2 Constructor & Destructor Documentation

7.22.2.1 **JpegOption**() [inline]

7.22.3 Property Documentation

7.22.3.1 bool progressive

Whether to save as a progressive JPEG file.

7.22.3.2 unsigned int quality

JPEG image quality in range (0-100).

- 100 Superb quality.
- 75 Good quality.
- 50 Normal quality.
- 10 Poor quality.

7.23 Jpg2Option Struct Reference

Options for saving JPEG2000 image.

Public Member Functions

• Jpg2Option ()

Properties

• unsigned int quality

JPEG saving quality in range (1-512).

7.23.1 Detailed Description

Options for saving JPEG2000 image.

7.23.2 Constructor & Destructor Documentation

7.23.2.1 Jpg2Option() [inline]

7.23.3 Property Documentation

7.23.3.1 unsigned int quality

JPEG saving quality in range (1-512).

7.24 LutData Struct Reference

Information about the camera's look up table.

Properties

• bool supported

Flag indicating if LUT is supported.

• bool enabled

Flag indicating if LUT is enabled.

• unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

• unsigned int numChannels

The number of LUT channels per bank available.

• unsigned int inputBitDepth

The input bit depth of the LUT.

• unsigned int outputBitDepth

The output bit depth of the LUT.

• unsigned int numEntries

The number of entries in the LUT.

7.24.1 Detailed Description

Information about the camera's look up table.

7.24.2 Property Documentation

7.24.2.1 bool enabled

Flag indicating if LUT is enabled.

7.24.2.2 unsigned int inputBitDepth

The input bit depth of the LUT.

7.24.2.3 unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

7.24.2.4 unsigned int numChannels

The number of LUT channels per bank available.

7.24.2.5 unsigned int numEntries

The number of entries in the LUT.

7.24.2.6 unsigned int outputBitDepth

The output bit depth of the LUT.

7.24.2.7 bool supported

Flag indicating if LUT is supported.

7.25 ManagedAVIRecorder Class Reference

ManagedAVIRecorder provides the functionality for the user to record images to an AVI file.

Public Member Functions

- ManagedAVIRecorder ()
- ~ManagedAVIRecorder ()
- void AVIOpen (System::String^ fileName, AviOption^ option)

Open an AVI file in preparation for writing Images to disk.

• void AVIAppend (ManagedImage^ image)

Append an image to the AVI file.

• void AVIClose ()

Close the AVI file.

7.25.1 Detailed Description

ManagedAVIRecorder provides the functionality for the user to record images to an AVI file.

7.25.2 Constructor & Destructor Documentation

- 7.25.2.1 ManagedAVIRecorder ()
- 7.25.2.2 ~ManagedAVIRecorder ()

7.25.3 Member Function Documentation

7.25.3.1 void AVIAppend (ManagedImage^ image)

Append an image to the AVI file.

Parameters:

image The ManagedImage to append.

7.25.3.2 void AVIClose ()

Close the AVI file.

See also:

AVIOpen()

7.25.3.3 void AVIOpen (System::String^ fileName, AviOption^ option)

Open an AVI file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters:

fileName The filename of the AVI file. *option* Options to apply to the AVI file.

See also:

AVIClose()

7.26 ManagedBusManager Class Reference

ManagedBusManager provides the functionality for the user to get an PGRGuid for a desired camera or device easily.

Public Member Functions

- ManagedBusManager ()
- ~ManagedBusManager ()
- void FireBusReset (ManagedPGRGuid[^] guid)

Fire a bus reset.

• unsigned int GetNumOfCameras ()

Gets the number of cameras attached to the PC.

• ManagedPGRGuid^ GetCameraFromIPAddress (System::Net::IPAddress^ ipAddress)

Gets the ManagedPGRGuid for a camera with the specified IPv4 address.

• ManagedPGRGuid^ GetCameraFromIndex (unsigned int index)

Gets the ManagedPGRGuid for a camera on the PC.

• ManagedPGRGuid^ GetCameraFromSerialNumber (unsigned int serialNumber)

Gets the ManagedPGRGuid for a camera on the PC.

• unsigned int GetCameraSerialNumberFromIndex (unsigned int index)

Gets the serial number of the camera with the specified index.

• InterfaceType GetInterfaceTypeFromGuid (ManagedPGRGuid^ guid)

Gets the interface type associated with a ManagedPGRGuid.

• unsigned int GetNumOfDevices ()

Gets the number of devices.

ManagedPGRGuid[^] GetDeviceFromIndex (unsigned int index)

Gets the ManagedPGRGuid for a device.

• unsigned int ReadPhyRegister (ManagedPGRGuid^ guid, unsigned int page, unsigned int port, unsigned int address)

Read a phy register on the specified device.

• void WritePhyRegister (ManagedPGRGuid^ guid, unsigned int page, unsigned int port, unsigned int address, unsigned int regVal)

Write a phy register on the specified device.

• void RescanBus ()

Force a rescan of the buses.

• System::IntPtr RegisterCallback (EnumCallback^ hCallbackDelegate, ManagedCallbackType callbackType, System::IntPtr parameter)

Register a callback function that will be called when the specified callback event occurs.

• void UnregisterCallback (System::IntPtr callbackHandle)

Unregister a callback function.

Static Public Member Functions

 static void ForceIPAddressToCamera macAddress, System::Net::IPAddress^ ipAddress, System::Net::IPAddress^ subnetMask, System::Net::IPAddress^ defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

• static array< CameraInfo^ >^ DiscoverGigECameras ()

Discover all cameras connected to the network even if they reside on a different subnet.

Protected Member Functions

• !ManagedBusManager ()

Static Package Functions

• static void ConvertToNativeGuid (ManagedPGRGuid^ mgdPGRGuid, FlyCapture2::PGRGuid *pgrGuid)

Convert a ManagedPGRGuid to a native PGRGuid.

static void ConvertToManagedGuid (FlyCapture2::PGRGuid *pgrGuid, ManagedPGRGuid[^] mgdP-GRGuid)

Convert a native PGRGuid to a ManagedPGRGuid.

7.26.1 Detailed Description

ManagedBusManager provides the functionality for the user to get an PGRGuid for a desired camera or device easily.

Once the camera or device token is found, it can then be used to connect to the camera or device through the camera class or device class. In addition, the BusManager class provides the ability to be notified when a camera or device is added or removed or some event occurs on the PC.

7.26.2 Constructor & Destructor Documentation

- 7.26.2.1 ManagedBusManager ()
- 7.26.2.2 ~ManagedBusManager ()
- **7.26.2.3** !ManagedBusManager() [protected]

7.26.3 Member Function Documentation

7.26.3.1 void ConvertToManagedGuid (FlyCapture2::PGRGuid * pgrGuid, ManagedPGRGuid ^ mgdPGRGuid) [inline, static, package]

Convert a native PGRGuid to a ManagedPGRGuid.

Parameters:

```
pgrGuid The native PGRGuid.mgdPGRGuid The ManagedPGRGuid.
```

7.26.3.2 void ConvertToNativeGuid (ManagedPGRGuid^ mgdPGRGuid, FlyCapture2::PGRGuid * pgrGuid) [inline, static, package]

Convert a ManagedPGRGuid to a native PGRGuid.

Parameters:

```
mgdPGRGuid The ManagedPGRGuid.
pgrGuid The native PGRGuid.
```

7.26.3.3 array < CameraInfo $^{\land} >$ DiscoverGigECameras () [static]

Discover all cameras connected to the network even if they reside on a different subnet.

This is useful in situations where a GigE camera is using Persistent IP and the application's subnet is different from the device subnet. After discovering the camera, it is easy to use ForceIPAddressToCamera() to set a different IP configuration.

Returns:

Array of CameraInfo structures containing information about discovered cameras.

7.26.3.4 void FireBusReset (ManagedPGRGuid^{\(\)} guid)

Fire a bus reset.

The actual bus reset is only fired for the specified 1394 bus, but it will effectively cause a global bus reset for the library.

Parameters:

guid ManagedPGRGuid of the camera or the device to cause bus reset.

7.26.3.5 void ForceIPAddressToCamera (System::Net::NetworkInformation::PhysicalAddress^ macAddress, System::Net::IPAddress^ ipAddress, System::Net::IPAddress^ subnetMask, System::Net::IPAddress^ defaultGateway) [static]

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

This is useful in situations where a GigE Vision camera is using Persistent IP and the application's subnet is different from the device subnet.

Parameters:

```
macAddress MAC address of the camera.ipAddress IP address to set on the camera.subnetMask Subnet mask to set on the camera.defaultGateway Default gateway to set on the camera.
```

7.26.3.6 ManagedPGRGuid GetCameraFromIndex (unsigned int index)

Gets the ManagedPGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the index and is used to identify the camera during a ManagedCamera::Connect() call.

Parameters:

index Zero based index of camera.

Returns:

Unique ManagedPGRGuid for the camera.

7.26.3.7 ManagedPGRGuid GetCameraFromIPAddress (System::Net::IPAddress^ ipAddress)

Gets the ManagedPGRGuid for a camera with the specified IPv4 address.

Parameters:

ipAddress IP address to get ManagedPGRGuid for.

Returns:

Unique ManagedPGRGuid for the camera.

7.26.3.8 ManagedPGRGuid GetCameraFromSerialNumber (unsigned int serialNumber)

Gets the ManagedPGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the serial number and is used to identify the camera during a ManagedCamera::Connect() call.

Parameters:

serialNumber Serial number of camera.

See also:

GetCameraFromIndex()

Returns:

Unique ManagedPGRGuid for the camera.

7.26.3.9 unsigned int GetCameraSerialNumberFromIndex (unsigned int *index*)

Gets the serial number of the camera with the specified index.

Parameters:

index Zero based index of desired camera.

Returns:

Serial number of camera.

7.26.3.10 ManagedPGRGuid GetDeviceFromIndex (unsigned int index)

Gets the ManagedPGRGuid for a device.

It uniquely identifies the device specified by the index.

Parameters:

index Zero based index of device.

See also:

GetNumOfDevices()

Returns:

Unique ManagedPGRGuid for the device.

7.26.3.11 InterfaceType GetInterfaceTypeFromGuid (ManagedPGRGuid^ guid)

Gets the interface type associated with a ManagedPGRGuid.

This is useful in situations where there is a need to enumerate all cameras for a particular interface.

Parameters:

guid The ManagedPGRGuid to get the interface for.

Returns:

The interface type of the PGRGuid.

7.26.3.12 unsigned int GetNumOfCameras ()

Gets the number of cameras attached to the PC.

Returns:

The number of cameras attached.

7.26.3.13 unsigned int GetNumOfDevices ()

Gets the number of devices.

This may include hubs, host controllers and other hardware devices (including cameras).

Returns:

The number of devices found.

7.26.3.14 unsigned int ReadPhyRegister (ManagedPGRGuid^ guid, unsigned int page, unsigned int port, unsigned int address)

Read a phy register on the specified device.

The full address to be read from is determined by the page, port and address.

Parameters:

```
guid ManagedPGRGuid of the device to read from.page Page to read from.port Port to read from.address Address to read from.
```

Returns:

Value read from the phy register.

7.26.3.15 System::IntPtr RegisterCallback (EnumCallback^ hCallbackDelegate, ManagedCallbackType callbackType, System::IntPtr parameter)

Register a callback function that will be called when the specified callback event occurs.

Parameters:

```
hCallbackDelegate Handle to EnumCallback function to receive the callback.callbackType Type of callback to register for.parameter Callback parameter to be passed to callback.
```

See also:

UnregisterCallback()

Returns:

Unique callback handle used for unregistering callback.

7.26.3.16 void RescanBus ()

Force a rescan of the buses.

This does not trigger a bus reset. However, any current connections to a ManagedCamera object will be invalidated.

7.26.3.17 void UnregisterCallback (System::IntPtr callbackHandle)

Unregister a callback function.

Parameters:

callbackHandle Unique callback handle.

See also:

RegisterCallback()

7.26.3.18 void WritePhyRegister (ManagedPGRGuid^ guid, unsigned int page, unsigned int port, unsigned int address, unsigned int regVal)

Write a phy register on the specified device.

The full address to be written to is determined by the page, port and address.


Parameters:

```
guid ManagedPGRGuid of the device to write to.
page Page to write to.
port Port to write to.
address Address to write to.
regVal Value to write to phy register.
```


7.27 ManagedCamera Class Reference

ManagedCamera represents a physical camera that uses the IIDC register set.

Inheritance diagram for ManagedCamera:



Collaboration diagram for ManagedCamera:



Public Member Functions

- ManagedCamera ()
- ~ManagedCamera ()

Protected Member Functions

• !ManagedCamera ()

DCAM Formats

These functions deal with DCAM video mode and frame rate on the camera.

- bool GetVideoModeAndFrameRateInfo (VideoMode videoMode, FrameRate frameRate)

 Query the camera to determine if the specified video mode and frame rate is supported.
- void GetVideoModeAndFrameRate (VideoMode% videoMode, FrameRate% frameRate)

 Get the current video mode and frame rate from the camera.

• void SetVideoModeAndFrameRate (VideoMode videoMode, FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

Format7

These functions deal with Format7 custom image control on the camera.

• Format7Info[^] GetFormat7Info (Mode mode, bool% supported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

• Format7PacketInfo^ ValidateFormat7Settings (Format7ImageSettings^ imageSettings, bool% settingsAreValid)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

• void GetFormat7Configuration (Format7ImageSettings^ imageSettings, unsigned int% packetSize, float% percentSpeed)

Get the current Format7 configuration from the camera.

• void SetFormat7Configuration (Format7ImageSettings^ imageSettings, unsigned int recommended-PacketSize)

Set the current Format7 configuration to the camera.

• void SetFormat7Configuration (Format7ImageSettings^ imageSettings, float recommendedPercentSpeed)

Set the current Format7 configuration to the camera.

7.27.1 Detailed Description

ManagedCamera represents a physical camera that uses the IIDC register set.

The object must first be connected to using Connect() before any other operations can proceed.

It is possible for more than 1 Camera object to connect to a single physical camera. However, isochronous transmission to more than 1 Camera object is not supported.

7.27.2 Constructor & Destructor Documentation

- 7.27.2.1 ManagedCamera ()
- 7.27.2.2 ~ManagedCamera ()
- **7.27.2.3** !ManagedCamera() [protected]

7.27.3 Member Function Documentation

7.27.3.1 void GetFormat7Configuration (Format7ImageSettings^ imageSettings, unsigned int% packetSize, float% percentSpeed)

Get the current Format7 configuration from the camera.

This call will only succeed if the camera is already in Format7.

Parameters:

```
image Settings Current image settings.packetSize Current packet size.percentSpeed Current packet size as a percentage.
```

See also:

```
GetFormat7Info()
ValidateFormat7Settings()
SetFormat7Configuration()
GetVideoModeAndFrameRate()
```

7.27.3.2 Format7Info GetFormat7Info (Mode mode, bool% supported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

The mode must be specified in the Format7Info structure in order for the function to succeed.

Parameters:

```
mode Format7 mode to query.supported Whether the specified mode is supported.
```

See also:

```
ValidateFormat7Settings()
GetFormat7Configuration()
SetFormat7Configuration()
```

Returns:

Format7Info structure filled with the capabilities of the specified mode and the current state in the specified mode.

7.27.3.3 void GetVideoModeAndFrameRate (VideoMode% videoMode, FrameRate% frameRate)

Get the current video mode and frame rate from the camera.

If the camera is in Format7, the video mode will be VIDEOMODE_FORMAT7 and the frame rate will be FRAMERATE FORMAT7.

Parameters:

```
videoMode Current video mode.frameRate Current frame rate.
```

See also:

GetVideoModeAndFrameRateInfo() SetVideoModeAndFrameRate()

7.27.3.4 bool GetVideoModeAndFrameRateInfo (VideoMode videoMode, FrameRate frameRate)

Query the camera to determine if the specified video mode and frame rate is supported.

Parameters:

```
videoMode Video mode to check.frameRate Frame rate to check.
```

See also:

```
GetVideoModeAndFrameRate()
SetVideoModeAndFrameRate()
```

Returns:

Whether the video mode and frame rate is supported.

7.27.3.5 void SetFormat7Configuration (Format7ImageSettings^ imageSettings, float recommendedPercentSpeed)

Set the current Format7 configuration to the camera.

Parameters:

```
image Settings Image settings to be written to the camera.recommendedPercentSpeed Percentage of packet size to be written to the camera.
```

See also:

```
GetFormat7Info()
ValidateFormat7Settings()
GetFormat7Configuration()
```

7.27.3.6 void SetFormat7Configuration (Format7ImageSettings^ imageSettings, unsigned int recommendedPacketSize)

Set the current Format7 configuration to the camera.

Parameters:

image Settings Image settings to be written to the camera.
recommendedPacketSize Packet size to be written to the camera.

See also:

GetFormat7Info()
ValidateFormat7Settings()
GetFormat7Configuration()

7.27.3.7 void SetVideoModeAndFrameRate (VideoMode videoMode, FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

It is not possible to set the camera to VIDEOMODE_FORMAT7 or FRAMERATE_FORMAT7. Use the Format7 functions to set the camera into Format7.

Parameters:

```
videoMode Video mode to set to camera.frameRate Frame rate to set to camera.
```

See also:

GetVideoModeAndFrameRateInfo()
GetVideoModeAndFrameRate()

7.27.3.8 Format7PacketInfo ValidateFormat7Settings (Format7ImageSettings^ imageSettings, bool% settingsAreValid)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

The current image settings are cached while validation is taking place. The cached settings are restored when validation is complete.

Parameters:

```
imageSettings Structure containing the image settings. settingsAreValid Whether the settings are valid.
```

See also:


GetFormat7Info()
GetFormat7Configuration()
SetFormat7Configuration()

Returns:

Packet size information that can be used to determine a valid packet size.

7.28 ManagedCameraBase Class Reference

Abstract base class that represents a generic camera that defines a general interface to a camera. Inheritance diagram for ManagedCameraBase:



Public Member Functions

- ManagedCameraBase ()
- virtual ~ManagedCameraBase ()

Connection and Image Retrieval

These functions deal with connections and image retrieval from the camera.

- virtual void Connect (ManagedPGRGuid[^] mgdPGRGuid)
 Connects the ManagedCamera object to the camera specified by the GUID.
- virtual void Disconnect ()
 Disconnects the ManagedCamera object from the camera.
- virtual bool IsConnected ()

 Checks if the ManagedCamera object is currently connected to a physical camera.
- virtual void SetCallback (ImageEventCallback^ hCallbackDelegate)

 Sets the callback data to be used on completion of image transfer.
- virtual void StartCapture ()
 Starts isochronous image capture.
- virtual void StartCapture (ImageEventCallback^ hCallbackDelegate)

 Starts isochronous image capture.
- virtual void StopCapture ()
 Stops isochronous image transfer and cleans up all associated resources.
- virtual void RetrieveBuffer (ManagedImage^ image)

 Retrieves the the next image object containing the next image.
- virtual void WaitForBufferEvent (ManagedImage^ image, unsigned int eventNumber)

 Retrieves the next image event containing the next part of the image.
- virtual FC2Config[^] GetConfiguration ()
 Get the configuration associated with the camera object.

• virtual void SetConfiguration (FC2Config^ config)

Set the configuration associated with the camera object.

Information and Properties

These functions deal with information and properties can be retrieved from the camera.

- virtual CameraInfo^ GetCameraInfo ()

 Retrieves information from the camera such as serial number, model name and other camera information.
- virtual CameraPropertyInfo^ GetPropertyInfo (PropertyType type)

 Retrieves information about the specified camera property.
- virtual CameraProperty \(^\text{ GetProperty (PropertyType type)}\)

 Reads the settings for the specified property from the camera.
- virtual void SetProperty (CameraProperty[^] camProperty)
 Writes the settings for the specified property to the camera.
- virtual void SetProperty (CameraProperty[^] camProperty, bool broadcast)
 Writes the settings for the specified property to the camera.

General Purpose Input / Output

These functions deal with general GPIO pin control on the camera.

- virtual unsigned int GetGPIOPinDirection (unsigned int pin) Get the GPIO pin direction for the specified pin.
- virtual void SetGPIOPinDirection (unsigned int pin, unsigned int direction) Set the GPIO pin direction for the specified pin.
- virtual void SetGPIOPinDirection (unsigned int pin, unsigned int direction, bool broadcast) Set the GPIO pin direction for the specified pin.

Trigger

These functions deal with trigger control on the camera.

- virtual TriggerModeInfo[^] GetTriggerModeInfo () Retrieve trigger information from the camera.
- virtual TriggerMode \(^\) GetTriggerMode ()

 Retrieve current trigger settings from the camera.
- virtual void SetTriggerMode (TriggerMode[^] triggerMode)

 Set the specified trigger settings to the camera.
- virtual void FireSoftwareTrigger (bool broadcast)
 Fire the software trigger according to the DCAM specifications.

Strobe

These functions deal with strobe control on the camera.

- virtual StrobeInfo[^] GetStrobeInfo (unsigned int source)
 Retrieve strobe information from the camera.
- virtual StrobeControl[^] GetStrobe (unsigned int source)

 Retrieve current strobe settings from the camera.
- virtual void SetStrobe (StrobeControl^ strobeControl)

 Set current strobe settings to the camera.

Look Up Table

These functions deal with Look Up Table control on the camera.

- virtual LutData^ GetLUTInfo ()

 Query if LUT support is available on the camera.
- virtual void GetLUTBankInfo (unsigned int bank, bool% readSupported, bool% writeSupported)

Query the read/write status of a single LUT bank.

- virtual unsigned int GetActiveLUTBank ()

 Get the LUT bank that is currently being used.
- virtual void SetActiveLUTBank (unsigned int activeBank)
 Set the LUT bank that will be used.
- virtual void EnableLUT (bool on)

 Enable or disable LUT functionality on the camera.
- virtual void GetLUTChannel (unsigned int bank, unsigned int channel, unsigned int sizeEntries, array< unsigned int >^entries)

Get the LUT channel settings from the camera.

• virtual void SetLUTChannel (unsigned int bank, unsigned int channel, unsigned int sizeEntries, array< unsigned int >^entries)

Set the LUT channel settings to the camera.

Memory Channels

These functions deal with memory channel control on the camera.

- virtual unsigned int GetMemoryChannel ()

 Retrieve the current memory channel from the camera.
- virtual void SaveToMemoryChannel (unsigned int channel)

 Save the current settings to the specfied current memory channel.
- virtual void RestoreFromMemoryChannel (unsigned int channel)

 Restore the specified current memory channel.
- virtual unsigned int GetMemoryChannelInfo ()

 Query the camera for memory channel support.

Embedded Image Information

These functions deal with embedded image information control on the camera.

virtual EmbeddedImageInfo^ GetEmbeddedImageInfo ()
 Get the current status of the embedded image information register, as well as the availability of each embedded property.

virtual void SetEmbeddedImageInfo (EmbeddedImageInfo[^] info)
 Sets the on/off values of the embedded image information structure to the camera.

Register Operation

These functions deal with register operation on the camera.

- virtual void WriteRegister (unsigned int address, unsigned int value) Write to the specified register on the camera.
- virtual void WriteRegister (unsigned int address, unsigned int value, bool broadcast) Write to the specified register on the camera.
- virtual unsigned int ReadRegister (unsigned int address)

 Read the specified register from the camera.
- virtual void WriteRegisterBlock (unsigned short addressHigh, unsigned int addressLow, array
 unsigned int >^buffer)

Write to the specified register block on the camera.

virtual void ReadRegisterBlock (unsigned short addressHigh, unsigned int addressLow, array
 unsigned int >^buffer)

Read from the specified register block on the camera.

Protected Member Functions

• void OnNativeCallback (FlyCapture2::Image *pImage, void *pCallbackData)

Protected Attributes

- FlyCapture2::CameraBase * m_pNativeCamBase
- ImageEventCallback ^ m_externalDelegate
- ImageCallbackDelegate^ m_internalDelegate

Package Functions

• FlyCapture2::CameraBase * GetNativeCamera ()

7.28.1 Detailed Description

Abstract base class that represents a generic camera that defines a general interface to a camera.

7.28.2 Constructor & Destructor Documentation

```
7.28.2.1 ManagedCameraBase() [inline]
```

7.28.2.2 virtual ~ ManagedCameraBase () [inline, virtual]

7.28.3 Member Function Documentation

7.28.3.1 void Connect (ManagedPGRGuid) [virtual]

Connects the ManagedCamera object to the camera specified by the GUID.

Parameters:

mgdPGRGuid The unique identifier for a specific camera on the PC.

See also:

```
ManagedBusManager::GetCameraFromIndex()
ManagedBusManager::GetCameraFromSerialNumber()
```

7.28.3.2 void Disconnect () [virtual]

Disconnects the ManagedCamera object from the camera.

This allows another physical camera to be connected to the ManagedCamera object.

See also:

Connect()

7.28.3.3 void EnableLUT (bool on) [virtual]

Enable or disable LUT functionality on the camera.

Parameters:

on Whether to enable or disable LUT.

See also:

```
GetLUTInfo()
GetLUTChannel()
SetLUTChannel()
```

7.28.3.4 void FireSoftwareTrigger (bool broadcast) [virtual]

Fire the software trigger according to the DCAM specifications.

Parameters:

broadcast Whether the action should be broadcast.

7.28.3.5 unsigned int GetActiveLUTBank () [virtual]

Get the LUT bank that is currently being used.

For cameras with PGR LUT, the active bank is always 0.

Returns:

The currently active bank.

7.28.3.6 CameraInfo GetCameraInfo () [virtual]

Retrieves information from the camera such as serial number, model name and other camera information.

Returns:

Structure containing camera information.

7.28.3.7 FC2Config GetConfiguration () [virtual]

Get the configuration associated with the camera object.

See also:

SetConfiguration()

Returns:

Current configuration.

7.28.3.8 EmbeddedImageInfo GetEmbeddedImageInfo () [virtual]

Get the current status of the embedded image information register, as well as the availability of each embedded property.

See also:

SetEmbeddedImageInfo()

Returns:

EmbeddedImageInfo structure containing embedded image information.

7.28.3.9 unsigned int GetGPIOPinDirection (unsigned int *pin***)** [virtual]

Get the GPIO pin direction for the specified pin.

This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

Parameters:

pin Pin to get the direction for.

See also:

SetGPIOPinDirection()

Returns:

Direction of the pin. 0 for input, 1 for output.

7.28.3.10 void GetLUTBankInfo (unsigned int bank, bool% readSupported, bool% writeSupported) [virtual]

Query the read/write status of a single LUT bank.

Parameters:

```
bank The bank to query.readSupported Whether reading from the bank is supported.writeSupported Whether writing to the bank is supported.
```

7.28.3.11 void GetLUTChannel (unsigned int bank, unsigned int channel, unsigned int size Entries, array< unsigned int $>^{\land}$ entries) [virtual]

Get the LUT channel settings from the camera.

Parameters:

```
bank Bank to retrieve.channel Channel to retrieve.sizeEntries Number of entries in LUT table to read.entries Array to store LUT entries in.
```

See also:

```
GetLUTInfo()
EnableLUT()
SetLUTChannel()
```

7.28.3.12 LutData GetLUTInfo () [virtual]

Query if LUT support is available on the camera.

See also:

```
EnableLUT()
GetLUTChannel()
SetLUTChannel()
```

Returns:

LutData structure containing the LUT information.

7.28.3.13 unsigned int GetMemoryChannel() [virtual]

Retrieve the current memory channel from the camera.

See also:

```
SaveToMemoryChannel()
RestoreFromMemoryChannel()
GetMemoryChannelInfo()
```

Returns:

Currently selected memory channel.

7.28.3.14 unsigned int GetMemoryChannelInfo() [virtual]

Query the camera for memory channel support.

If the number of channels is 0, then memory channel support is not available.

See also:

```
GetMemoryChannel()
SaveToMemoryChannel()
RestoreFromMemoryChannel()
```

Returns:

Number of memory channels supported.

```
7.28.3.15 FlyCapture2::CameraBase * GetNativeCamera () [package]
```

7.28.3.16 CameraProperty GetProperty (PropertyType type) [virtual]

Reads the settings for the specified property from the camera.

If auto is on, the integer and abs values returned may not be consistent with each other.

Parameters:

type The PropertyType to retrieve information about.

See also:

```
GetPropertyInfo()
SetProperty()
```

Returns:

Property structure containing property information.

7.28.3.17 CameraPropertyInfo GetPropertyInfo (PropertyType type) [virtual]

Retrieves information about the specified camera property.

Parameters:

type The PropertyType to retrieve information about.

See also:

```
GetProperty()
SetProperty()
```

Returns:

PropertyInfo structure containing property information.

7.28.3.18 StrobeControl GetStrobe (unsigned int source) [virtual]

Retrieve current strobe settings from the camera.

Parameters:

source Source pin for strobe information.

See also:

```
GetStrobeInfo()
SetStrobe()
```

Returns:

StrobeControl structure containing strobe information.

7.28.3.19 StrobeInfo GetStrobeInfo (unsigned int source) [virtual]

Retrieve strobe information from the camera.

Parameters:

source Source pin for strobe information.

See also:

```
GetStrobe()
SetStrobe()
```

Returns:

StrobeInfo structure containing strobe information.

7.28.3.20 TriggerMode GetTriggerMode () [virtual]

Retrieve current trigger settings from the camera.

See also:

```
GetTriggerModeInfo()
SetTriggerMode()
```

Returns:

TriggerMode structure containing trigger mode settings.

7.28.3.21 TriggerModeInfo GetTriggerModeInfo() [virtual]

Retrieve trigger information from the camera.

See also:

```
GetTriggerMode()
SetTriggerMode()
```

Returns:

TriggerModeInfo structure containing receive trigger information.

7.28.3.22 bool IsConnected () [virtual]

Checks if the ManagedCamera object is currently connected to a physical camera.

See also:

```
Connect()
Disconnect()
```

Returns:

Whether the ManagedCamera object is connected to a physical camera.

7.28.3.23 void OnNativeCallback (FlyCapture2::Image * *pImage*, **void** * *pCallbackData*) [protected]

7.28.3.24 unsigned int ReadRegister (unsigned int address) [virtual]

Read the specified register from the camera.

Parameters:

address DCAM address to be read from.

See also:

WriteRegister()

Returns:

The register value that is read.

7.28.3.25 void ReadRegisterBlock (unsigned short addressHigh, unsigned int addressLow, array< unsigned int >^ buffer) [virtual]

Read from the specified register block on the camera.

Parameters:

```
addressHigh Top 16 bits of the 48 bit absolute address to read from.addressLow Bottom 32 bits of the 48 bits absolute address to read from.buffer Array to store read data.
```

See also:

WriteRegisterBlock()

7.28.3.26 void RestoreFromMemoryChannel (unsigned int *channel***)** [virtual]

Restore the specfied current memory channel.

Parameters:

channel Memory channel to restore from.

See also:

```
GetMemoryChannel()
SaveToMemoryChannel()
GetMemoryChannelInfo()
```

7.28.3.27 void RetrieveBuffer (ManagedImage *image*) [virtual]

Retrieves the the next image object containing the next image.

If the grab mode has not been set, or has been set to DROP_FRAMES the default behavior is to requeue images for DMA if they have not been retrieved by the time the next image transfer completes. If BUFFER_FRAMES is specified, the next image in the sequence will be retrieved. Note that for the BUFFER_FRAMES case, if retrieval does not keep up with the DMA process, images will be lost. The default behavior is to perform DROP_FRAMES image retrieval.

Parameters:

image ManagedImage object to store image data.

See also:

```
StartCapture()
StopCapture()
WaitForBufferEvent()
```

7.28.3.28 void SaveToMemoryChannel (unsigned int *channel***)** [virtual]

Save the current settings to the specfied current memory channel.

Parameters:

channel Memory channel to save to.

See also:

GetMemoryChannel()
RestoreFromMemoryChannel()
GetMemoryChannelInfo()

7.28.3.29 void SetActiveLUTBank (unsigned int *activeBank*) [virtual]

Set the LUT bank that will be used.

Parameters:

activeBank The bank to be set as active.

7.28.3.30 void SetCallback (**ImageEventCallback** *hCallbackDelegate*) [virtual]

Sets the callback data to be used on completion of image transfer.

To clear the current stored callback data, pass in NULL as the argument.

Parameters:

hCallbackDelegate A function to be called when a new image is received.

See also:

StartCapture()

Returns:

An Error indicating the success or failure of the function.

7.28.3.31 void SetConfiguration (FC2Config^ config) [virtual]

Set the configuration associated with the camera object.

Parameters:

config Configuration structure to be used.

See also:

GetConfiguration()

7.28.3.32 void SetEmbeddedImageInfo (EmbeddedImageInfo^ info) [virtual]

Sets the on/off values of the embedded image information structure to the camera.

Parameters:

info Structure to be used.

See also:

GetEmbeddedImageInfo()

7.28.3.33 void SetGPIOPinDirection (unsigned int pin, unsigned int direction, bool broadcast) [virtual]

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

Parameters:

```
pin Pin to get the direction for.direction Direction of the pin. 0 for input, 1 for output.broadcast Whether the action should be broadcast.
```

See also:

GetGPIOPinDirection()

7.28.3.34 void SetGPIOPinDirection (unsigned int *pin***, unsigned int** *direction*) [virtual]

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

Parameters:

```
pin Pin to get the direction for.direction Direction of the pin. 0 for input, 1 for output.
```

See also:

GetGPIOPinDirection()

7.28.3.35 void SetLUTChannel (unsigned int bank, unsigned int channel, unsigned int sizeEntries, array< unsigned int $>^{\land}$ entries) [virtual]

Set the LUT channel settings to the camera.

Parameters:

```
bank Bank to set.channel Channel to set.sizeEntries Number of entries in LUT table to write.entries Array containing LUT entries to write.
```

See also:

```
GetLUTInfo()
EnableLUT()
GetLUTChannel()
```

7.28.3.36 void SetProperty (CameraProperty camProperty, bool broadcast) [virtual]

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera.

Parameters:

```
camProperty CameraProperty structure to be used. broadcast Whether the action should be broadcast.
```

See also:

```
GetPropertyInfo()
GetProperty()
```

7.28.3.37 void SetProperty (CameraProperty *camProperty*) [virtual]

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera.

Parameters:

```
camProperty CameraProperty structure to be used.
```

See also:

```
GetPropertyInfo()
GetProperty()
```

7.28.3.38 void SetStrobe (StrobeControl) [virtual]

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

Parameters:

strobeControl Structure providing strobe settings.

See also:

```
GetStrobe()
GetStrobe()
```

7.28.3.39 void SetTriggerMode (TriggerMode^ triggerMode) [virtual]

Set the specified trigger settings to the camera.

Parameters:

triggerMode Structure providing trigger mode settings.

See also:

```
GetTriggerModeInfo()
GetTriggerMode()
```

7.28.3.40 void StartCapture (ImageEventCallback *hCallbackDelegate*) [virtual]

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera. The callback function parameter is called on completion of image transfer.

Parameters:

hCallbackDelegate A function to be called when a new image is received.

See also:

```
RetrieveBuffer()
StopCapture()
```

7.28.3.41 void StartCapture() [virtual]

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera. RetrieveBuffer() can be called to get the image data.

See also:

```
RetrieveBuffer()
StopCapture()
```

7.28.3.42 void StopCapture () [virtual]

Stops isochronous image transfer and cleans up all associated resources.

See also:

```
StartCapture()
RetrieveBuffer()
```

7.28.3.43 void WaitForBufferEvent (**ManagedImage**^ *image*, **unsigned int** *eventNumber*) [virtual]

Retrieves the next image event containing the next part of the image.

Parameters:

```
pImage ManagedImage object to store image data.
eventNumber The event number to wait for.
```

See also:

RetrieveBuffer

7.28.3.44 void WriteRegister (**unsigned** int *address*, **unsigned** int *value*, **bool** *broadcast*)

Write to the specified register on the camera.

Parameters:

```
address DCAM address to be written to.value The value to be written.broadcast Whether the action should be broadcast.
```

See also:

ReadRegister()

7.28.3.45 void WriteRegister (unsigned int *address***, unsigned int** *value***)** [virtual]

Write to the specified register on the camera.

Parameters:

```
address DCAM address to be written to.value The value to be written.
```

See also:

ReadRegister()

7.28.3.46 void WriteRegisterBlock (unsigned short addressHigh, unsigned int addressLow, array< unsigned int >^ buffer) [virtual]

Write to the specified register block on the camera.

Parameters:

```
addressHigh Top 16 bits of the 48 bit absolute address to write to.addressLow Bottom 32 bits of the 48 bits absolute address to write to.buffer Array containing data to be written.
```

See also:


ReadRegisterBlock()

7.28.4 Member Data Documentation


- **7.28.4.1** ImageEventCallback ^ m_externalDelegate [protected]
- **7.28.4.2** ImageCallbackDelegate ^ m_internalDelegate [protected]
- **7.28.4.3 FlyCapture2::CameraBase*** m_pNativeCamBase [protected]

7.29 ManagedGigECamera Class Reference

The GigECamera object represents a physical Gigabit Ethernet camera. Inheritance diagram for ManagedGigECamera:



Collaboration diagram for ManagedGigECamera:



Public Member Functions

- ManagedGigECamera ()
- ~ManagedGigECamera ()

Protected Member Functions

• !ManagedGigECamera ()

GVCP Register Operation

These functions deal with GVCP register operation on the camera.

- void WriteGVCPRegister (unsigned int address, unsigned int value) Write a GVCP register.
- void WriteGVCPRegister (unsigned int address, unsigned int value, bool broadcast) Write a GVCP register.

- unsigned int ReadGVCPRegister (unsigned int address)

 Read a GVCP register.
- void WriteGVCPRegisterBlock (unsigned int address, array< unsigned int >^buffer) Write a GVCP register block.
- void ReadGVCPRegisterBlock (unsigned int address, array< unsigned int >^buffer) Read a GVCP register block.
- void WriteGVCPMemory (unsigned int address, array< unsigned char >^buffer) Write a GVCP memory block.
- void ReadGVCPMemory (unsigned int address, array< unsigned char >^buffer)

 Read a GVCP memory block.

GigE property manipulation

These functions deal with GigE properties.

- GigEProperty GetGigEProperty (GigEPropertyType propType)

 Get the specified GigEProperty.
- void SetGigEProperty (GigEProperty^ prop)

 Set the specified GigEProperty.
- unsigned int DiscoverGigEPacketSize ()

 Discover the largest packet size that works for the network link between the PC and the camera.

GigE image settings

These functions deal with GigE image setting.

- bool QueryGigEImagingMode (Mode mode)

 Check if the particular imaging mode is supported by the camera.
- Mode GetGigEImagingMode ()

 Get the current imaging mode on the camera.
- void SetGigEImagingMode (Mode mode)

 Set the current imaging mode to the camera.
- GigEImageSettingsInfo^ GetGigEImageSettingsInfo ()

 Get information about the image settings possible on the camera.
- GigEImageSettings \(^\) GetGigEImageSettings ()

 Get the current image settings on the camera.

void SetGigEImageSettings (GigEImageSettings[^] settings)

Set the image settings specified to the camera.

GigE image binning settings

These functions deal with GigE image binning setting.

• void GetGigEImageBinningSettings (unsigned int% horzBinningValue, unsigned int% vertBinning-Value)

Get the current binning settings on the camera.

• void SetGigEImageBinningSettings (unsigned int horzBinnningValue, unsigned int vertBinnning-Value)

Set the specified binning values to the camera.

GigE image stream configuration

These functions deal with GigE image stream configuration.

• unsigned int GetNumStreamChannels ()

Get the number of stream channels present on the camera.

• GigEStreamChannel^ GetGigEStreamChannelInfo (unsigned int channel)

Get the stream channel information for the specified channel.

• void SetGigEStreamChannelInfo (unsigned int channel, GigEStreamChannel^ channelInfo)

 $Set \ the \ stream \ channel \ information \ for \ the \ specified \ channel.$

7.29.1 Detailed Description

The GigECamera object represents a physical Gigabit Ethernet camera.

The object must first be connected to using Connect() before any other operations can proceed.

Please see ManagedCameraBase for basic functions that this class inherits from.

7.29.2 Constructor & Destructor Documentation

- 7.29.2.1 ManagedGigECamera ()
- 7.29.2.2 ~ManagedGigECamera ()
- **7.29.2.3** !ManagedGigECamera() [protected]

7.29.3 Member Function Documentation

7.29.3.1 unsigned int DiscoverGigEPacketSize ()

Discover the largest packet size that works for the network link between the PC and the camera.

This is useful in cases where there may be multiple links between the PC and the camera and there is a possibility of a component not supporting the recommended jumbo frame packet size of 9000.

Returns:

The maximum packet size supported by the link.

7.29.3.2 void GetGigEImageBinningSettings (unsigned int% horzBinningValue, unsigned int% vertBinningValue)

Get the current binning settings on the camera.

Parameters:

horzBinningValue Current horizontal binning value.vertBinningValue Current vertical binning value.

7.29.3.3 GigEImageSettings GetGigEImageSettings ()

Get the current image settings on the camera.

Returns:

Current image settings on camera.

7.29.3.4 GigEImageSettingsInfo GetGigEImageSettingsInfo ()

Get information about the image settings possible on the camera.

Returns:

Image settings information.

7.29.3.5 Mode GetGigEImagingMode ()

Get the current imaging mode on the camera.

Returns:

Current imaging mode on the camera.

7.29.3.6 GigEProperty GetGigEProperty (GigEPropertyType propType)

Get the specified GigEProperty.

Returns:

The GigE property to get.

7.29.3.7 GigEStreamChannel GetGigEStreamChannelInfo (unsigned int channel)

Get the stream channel information for the specified channel.

Parameters:

channel Channel number to use.

Returns:

Stream channel information for the specified channel.

7.29.3.8 unsigned int GetNumStreamChannels ()

Get the number of stream channels present on the camera.

Returns:

Number of stream channels present.

7.29.3.9 bool QueryGigEImagingMode (Mode mode)

Check if the particular imaging mode is supported by the camera.

Parameters:

mode The mode to check.

Returns:

Whether the mode is supported.

7.29.3.10 void ReadGVCPMemory (unsigned int address, array< unsigned char >^ buffer)

Read a GVCP memory block.

Parameters:

address GVCP address to be read from.buffer Array for data to be read into.length Size of array, in quadlets.

7.29.3.11 unsigned int ReadGVCPRegister (unsigned int address)

Read a GVCP register.

Parameters:

address GVCP address to be read from.

Returns:

The value that is read.

7.29.3.12 void ReadGVCPRegisterBlock (unsigned int address, array< unsigned int $>^{\land}$ buffer)

Read a GVCP register block.

Parameters:

address GVCP address to be read from.buffer Array for data to be read into.length Size of array, in quadlets.

7.29.3.13 void SetGigEImageBinningSettings (unsigned int horzBinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

It is recommended that GetGigEImageSettingsInfo() be called after this function succeeds to retrieve the new image settings information for the new binning mode.

Parameters:

horzBinnningValue Horizontal binning value.vertBinnningValue Vertical binning value.

7.29.3.14 void SetGigEImageSettings (GigEImageSettings^{\(\)} settings)

Set the image settings specified to the camera.

Parameters:

settings Image settings to set to camera.

7.29.3.15 void SetGigEImagingMode (Mode *mode*)

Set the current imaging mode to the camera.

This should only be done when the camera is not streaming images.

Parameters:

mode Imaging mode to set to the camera.

7.29.3.16 void SetGigEProperty (GigEProperty \(^prop\))

Set the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

Parameters:

prop The GigE property to set.

7.29.3.17 void SetGigEStreamChannelInfo (unsigned int *channel*, GigEStreamChannel[^] *channelInfo*)

Set the stream channel information for the specified channel.

Parameters:

channel Channel number to use.

channelInfo Stream channel information to use for the specified channel.

7.29.3.18 void WriteGVCPMemory (unsigned int address, array< unsigned char >^ buffer)

Write a GVCP memory block.

Parameters:

address GVCP address to be write to.

buffer Array containing data to be written.

length Size of array, in quadlets.

7.29.3.19 void WriteGVCPRegister (unsigned int address, unsigned int value, bool broadcast)

Write a GVCP register.

Parameters:

address GVCP address to be written to.

value The value to be written.

broadcast Whether the action should be broadcast.

7.29.3.20 void WriteGVCPRegister (unsigned int address, unsigned int value)

Write a GVCP register.

Parameters:

address GVCP address to be written to.value The value to be written.

7.29.3.21 void WriteGVCPRegisterBlock (unsigned int address, array< unsigned int >^ buffer)

Write a GVCP register block.

Parameters:

address GVCP address to be write to.buffer Array containing data to be written.length Size of array, in quadlets.

7.30 ManagedImage Class Reference

The ManagedImageImage class is used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Public Member Functions

- ManagedImage ()
- ManagedImage (unsigned int rows, unsigned int cols, unsigned int stride, unsigned char *pData, unsigned int dataSize, PixelFormat format)
- ManagedImage (unsigned int rows, unsigned int cols, unsigned int stride, unsigned char *pData, unsigned int dataSize, PixelFormat format, BayerTileFormat bayerFormat)
- ManagedImage (unsigned char *pData, unsigned int dataSize)
- ManagedImage (unsigned int rows, unsigned int cols, PixelFormat format)
- ManagedImage (unsigned int rows, unsigned int cols, PixelFormat format, BayerTileFormat bayer-Format)
- ManagedImage (ManagedImage^ image)
- ~ManagedImage ()
- void SetDimensions (unsigned int rows, unsigned int cols, unsigned int stride, PixelFormat pixelFormat, BayerTileFormat bayerFormat)

Sets the dimensions of the ManagedImage object.

- void SetData (unsigned char *pData, unsigned int dataSize)
 Set the data of the ManagedImage object.
- void CalculateStatistics (ManagedImageStatistics[^] statistics)

 Calculate statistics associated with the image.
- void Save (System::String^ fileName)
 Save the image to the specified file name.
- void Save (System::String^ fileName, ImageFileFormat format)

 Save the image to the specified file name with the file format specified.
- void Save (System::String^ fileName, PngOption option)

 Save the image to the specified file name with the options specified.
- void Save (System::String[^] fileName, PpmOption option)
 Save the image to the specified file name with the options specified.
- void Save (System::String[^] fileName, PgmOption option)
 Save the image to the specified file name with the options specified.
- void Save (System::String[^] fileName, TiffOption option)
 Save the image to the specified file name with the options specified.
- void Save (System::String[^] fileName, JpegOption option)
 Save the image to the specified file name with the options specified.
- void Save (System::String^ fileName, Jpg2Option option)

Save the image to the specified file name with the options specified.

- void Convert (ManagedImage^ destImage)
 - Converts the current image buffer and stores the result in the specified image.
- void Convert (PixelFormat format, ManagedImage[^] destImage)
 Converts the current image buffer to the specified output format and stores the result in the specified image.
- void ReleaseBuffer ()

Release the buffer associated with the ManagedImage.

• void * GetRawNativeImagePointer ()

Static Public Member Functions

• static unsigned int DetermineBitsPerPixel (PixelFormat format)

Calculate the bits per pixel for the specified pixel format.

Protected Member Functions

• !ManagedImage ()

Package Functions

- ManagedImage (FlyCapture2::Image &image)
- bool IsNativeImageValid ()
- FlyCapture2::Image * GetNativeImage ()

Properties

- static ColorProcessingAlgorithm defaultColorProcessingAlgorithm [get, set]

 The default color processing algorithm to be used.
- static PixelFormat defaultOutputPixelFormat [get, set]

 The default output pixel format to be used.
- ColorProcessingAlgorithm colorProcessingAlgorithm [get, set]

 Color processing algorithm to be used.
- PixelFormat pixelFormat [get]

 Pixel format of the image.
- BayerTileFormat bayerTileFormat [get]

Bayer tile format of the image.

• unsigned int cols [get]

Number of columns in the image.

```
• unsigned int rows [get]
     Number of rows in the image.
• unsigned int stride [get]
     Number of bytes between rows in the image.
• unsigned int bitsPerPixel [get]
     Number of bits per pixel in the image.
• unsigned char * data [get]
     Raw pointer to image data.
• ImageMetadata [get]
     Get the metadata associated with the image.
• TimeStamp [get]
     Get the timestamp data associated with the image.
• System::Drawing::Bitmap  [get]
```

Get the internal bitmap representation associated with the image.

7.30.1 Detailed Description

The ManagedImageImage class is used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Operations on Image objects are not guaranteed to be thread safe. It is recommended that operations on Image objects be protected by thread synchronization constructs such as mutexes.

7.30.2 Constructor & Destructor Documentation

- 7.30.2.1 ManagedImage ()
- 7.30.2.2 ManagedImage (unsigned int *rows*, unsigned int *cols*, unsigned int *stride*, unsigned char * pData, unsigned int dataSize, PixelFormat format)
- 7.30.2.3 ManagedImage (unsigned int rows, unsigned int cols, unsigned int stride, unsigned char * pData, unsigned int dataSize, PixelFormat format, BayerTileFormat bayerFormat)
- 7.30.2.4 ManagedImage (unsigned char * pData, unsigned int dataSize)
- 7.30.2.5 ManagedImage (unsigned int rows, unsigned int cols, PixelFormat format)
- 7.30.2.6 ManagedImage (unsigned int rows, unsigned int cols, PixelFormat format, BayerTileFormat bayerFormat)
- 7.30.2.7 ManagedImage (ManagedImage^{\(\)} image)
- 7.30.2.8 \sim ManagedImage ()
- **7.30.2.9 ManagedImage (FlyCapture2::Image & image)** [package]
- 7.30.2.10 !ManagedImage() [protected]

7.30.3 Member Function Documentation

7.30.3.1 void CalculateStatistics (ManagedImageStatistics^ statistics)

Calculate statistics associated with the image.

In order to collect statistics for a particular channel, the enabled flag for the channel must be set to true. Statistics can only be collected for images in Mono8, Mono16, RGB, RGBU, BGR and BGRU.

Parameters:

statistics The ManagedImageStatistics object to hold the statistics.

7.30.3.2 void Convert (PixelFormat format, ManagedImage^{\(\)} destImage)

Converts the current image buffer to the specified output format and stores the result in the specified image. The destination image does not need to be configured in any way before the call is made.

Parameters:

format Output format of the converted image. *destImage* Destination image.

7.30.3.3 void Convert (ManagedImage^{\(\right)} destImage)

Converts the current image buffer and stores the result in the specified image.

The destination image does not need to be configured in any way before the call is made.

Parameters:

destImage Destination image.

7.30.3.4 unsigned int DetermineBitsPerPixel (PixelFormat *format***)** [static]

Calculate the bits per pixel for the specified pixel format.

Parameters:

format The pixel format.

Returns:

The bits per pixel.

```
7.30.3.5 FlyCapture2::Image * GetNativeImage () [package]
```

```
7.30.3.6 void * GetRawNativeImagePointer ()
```

7.30.3.7 bool IsNativeImageValid () [package]

7.30.3.8 void ReleaseBuffer ()

Release the buffer associated with the ManagedImage.

If no buffer is associated, the function does nothing.

7.30.3.9 void Save (System::String^ fileName, Jpg2Option option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.10 void Save (System::String file Name, Jpeg Option option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.11 void Save (System::String fileName, TiffOption option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.12 void Save (System::String^ fileName, PgmOption option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.13 void Save (System::String fileName, PpmOption option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.14 void Save (System::String fileName, PngOption option)

Save the image to the specified file name with the options specified.

Parameters:

```
fileName Filename to save image with.

option Options to use while saving image.
```

7.30.3.15 void Save (System::String^ fileName, ImageFileFormat format)

Save the image to the specified file name with the file format specified.

Parameters:

```
fileName Filename to save image with.format File format to save in.
```

7.30.3.16 void Save (System::String^ fileName)

Save the image to the specified file name.

Parameters:

fileName Filename to save image with.

7.30.3.17 void SetData (unsigned char * pData, unsigned int dataSize)

Set the data of the ManagedImage object.

Ownership of the image buffer is not transferred to the ManagedImage object. It is the user's responsibility to delete the buffer when it is no longer in use.

Parameters:

```
pData Pointer to the image buffer.dataSize Size of the image buffer.
```

7.30.3.18 void SetDimensions (unsigned int *rows*, unsigned int *cols*, unsigned int *stride*, PixelFormat *pixelFormat*, BayerTileFormat *bayerFormat*)

Sets the dimensions of the ManagedImage object.

Parameters:

```
rows Number of rows to set.cols Number of cols to set.stride Stride to set.pixelFormat Pixel format to set.bayerFormat Bayer tile format to set.
```

7.30.4 Property Documentation

7.30.4.1 BayerTileFormat bayerTileFormat [get]

Bayer tile format of the image.

```
7.30.4.2 System:: Drawing:: Bitmap bitmap [get]
```

Get the internal bitmap representation associated with the image.

Returns:

A System::Drawing::Bitmap containing the image data.

7.30.4.3 unsigned int bitsPerPixel [get]

Number of bits per pixel in the image.

7.30.4.4 ColorProcessingAlgorithm colorProcessingAlgorithm [get, set]

Color processing algorithm to be used.

7.30.4.5 unsigned int cols [get]

Number of columns in the image.

7.30.4.6 unsigned char* data [get]

Raw pointer to image data.

7.30.4.7 ColorProcessingAlgorithm defaultColorProcessingAlgorithm [static, get, set]

The default color processing algorithm to be used.

7.30.4.8 PixelFormat defaultOutputPixelFormat [static, get, set]

The default output pixel format to be used.

7.30.4.9 ImageMetadata [get]

Get the metadata associated with the image.

This includes embedded image information.

Returns:

Metadata associated with the image.

7.30.4.10 PixelFormat pixelFormat [get]

Pixel format of the image.

7.30.4.11 unsigned int rows [get]

Number of rows in the image.

7.30.4.12 unsigned int stride [get]

Number of bytes between rows in the image.

7.30.4.13 TimeStamp^ timeStamp [get]

Get the timestamp data associated with the image.

Returns:

Timestamp data associated with the image.

7.31 ManagedImageStatistics Class Reference

Public Member Functions

- ManagedImageStatistics ()
- ~ManagedImageStatistics ()
- void EnableAll ()
- void DisableAll ()
- void EnableGreyOnly ()
- void EnableRGBOnly ()
- void EnableHSLOnly ()
- bool GetChannelStatus (StatisticsChannel channel)
- void SetChannelStatus (StatisticsChannel channel, bool enabled)
- void GetRange (StatisticsChannel channel, unsigned int% min, unsigned int% max)
- void GetPixelValueRange (StatisticsChannel channel, unsigned int% pixelValueMin, unsigned int% pixelValueMax)
- void GetNumPixelValues (StatisticsChannel channel, unsigned int% numPixelValues)
- void GetMean (StatisticsChannel channel, float% mean)
- void GetHistogram (StatisticsChannel channel, array< int >^histogram)
- void GetStatistics (StatisticsChannel channel, unsigned int% rangeMin, unsigned int% rangeMax, unsigned int% pixelValueMin, unsigned int% pixelValueMax, unsigned int% numPixelValues, float% mean, array<int>^histogram)

Package Functions

• FlyCapture2::ImageStatistics * GetNativeImageStatistics ()

7.31.1 Constructor & Destructor Documentation

- 7.31.1.1 ManagedImageStatistics ()
- 7.31.1.2 ~ManagedImageStatistics ()

7.31.2 Member Function Documentation

- 7.31.2.1 void DisableAll ()
- 7.31.2.2 void EnableAll ()
- 7.31.2.3 void EnableGreyOnly ()
- 7.31.2.4 void EnableHSLOnly ()
- 7.31.2.5 void EnableRGBOnly ()
- 7.31.2.6 bool GetChannelStatus (StatisticsChannel channel)
- 7.31.2.7 void GetHistogram (StatisticsChannel channel, array< int >^ histogram)
- 7.31.2.8 void GetMean (StatisticsChannel channel, float% mean)
- **7.31.2.9 FlyCapture2::ImageStatistics * GetNativeImageStatistics ()** [package]
- 7.31.2.10 void GetNumPixelValues (StatisticsChannel channel, unsigned int% numPixelValues)
- 7.31.2.11 void GetPixelValueRange (StatisticsChannel *channel*, unsigned int% *pixelValueMin*, unsigned int% *pixelValueMax*)
- 7.31.2.12 void GetRange (StatisticsChannel channel, unsigned int% min, unsigned int% max)
- 7.31.2.13 void GetStatistics (Statistics Channel channel, unsigned int% rangeMin, unsigned int% rangeMax, unsigned int% pixelValueMin, unsigned int% pixelValueMax, unsigned int% numPixelValues, float% mean, array< int >^ histogram)
- 7.31.2.14 void SetChannelStatus (StatisticsChannel channel, bool enabled)

7.32 ManagedPGRGuid Class Reference

Managed version of a PGRGuid.

Public Member Functions

• ManagedPGRGuid ()

Constructor.

ManagedPGRGuid (ManagedPGRGuid[∧] managedGuid)

Copy constructor.

• ManagedPGRGuid (ManagedPGRGuid% managedGuid)

Copy constructor.

• ManagedPGRGuid% operator= (ManagedPGRGuid% managedGuid)

Assignment operator.

- virtual bool Equals (Object^{\(\Lambda\)} obj) override
- virtual int GetHashCode () override

Static Public Member Functions

- static bool operator== (ManagedPGRGuid% left, ManagedPGRGuid% right)

 Equality operator.
- static bool operator!= (ManagedPGRGuid% left, ManagedPGRGuid% right)

 Inequality operator.

Package Attributes

- unsigned int value0
- unsigned int value1
- unsigned int value2
- unsigned int value3

7.32.1 Detailed Description

Managed version of a PGRGuid.

It is used to uniquely identify a camera.

7.32.2 Constructor & Destructor Documentation

7.32.2.1 ManagedPGRGuid () [inline]

Constructor.

7.32.2.2 ManagedPGRGuid (ManagedPGRGuid^ managedGuid) [inline]

Copy constructor.

7.32.2.3 ManagedPGRGuid (ManagedPGRGuid% managedGuid) [inline]

Copy constructor.

7.32.3 Member Function Documentation

- **7.32.3.1 virtual bool Equals (Object** $^{\wedge}$ *obj*) [inline, override, virtual]
- **7.32.3.2 virtual int GetHashCode**() [inline, override, virtual]

7.32.3.3 static bool operator!= (ManagedPGRGuid% left, ManagedPGRGuid% right) [inline, static]

Inequality operator.

7.32.3.4 ManagedPGRGuid % operator= (ManagedPGRGuid % managedGuid) [inline]

Assignment operator.

7.32.3.5 static bool operator== (ManagedPGRGuid% left, ManagedPGRGuid% right) [inline, static]

Equality operator.

7.32.4 Member Data Documentation

- **7.32.4.1 unsigned int value0** [package]
- **7.32.4.2 unsigned int value1** [package]
- **7.32.4.3 unsigned int value2** [package]
- **7.32.4.4 unsigned int value3** [package]

7.33 ManagedUtilities Class Reference

Static Public Member Functions

- static void LaunchBrowser (System::String^ address)
- static void LaunchHelp (System::String^ fileName)
- static void LaunchCommand (System::String^ command)

Properties

- static SystemInfo [get]
- static FC2Version^ libraryVersion [get]

7.33.1 Member Function Documentation

- **7.33.1.1 void LaunchBrowser (System::String** *address*) [static]
- **7.33.1.2 void LaunchCommand (System::String**^ *command*) [static]
- **7.33.1.3 void LaunchHelp (System::String** *fileName*) [static]

7.33.2 Property Documentation

- **7.33.2.1 FC2Version** [static, get]
- **7.33.2.2 SystemInfo** [static, get]

7.34 PgmOption Struct Reference

Options for saving PGM images.

Public Member Functions

• PgmOption ()

Properties

• bool binaryFile

Whether to save the PPM as a binary file.

7.34.1 Detailed Description

Options for saving PGM images.

7.34.2 Constructor & Destructor Documentation

7.34.2.1 PgmOption() [inline]

7.34.3 Property Documentation

7.34.3.1 bool binaryFile

Whether to save the PPM as a binary file.

7.35 PngOption Struct Reference

Options for saving PNG images.

Public Member Functions

• PngOption ()

Properties

• bool interlaced

Whether to save the PNG as interlaced.

• unsigned int compressionLevel

Compression level (0-9).

7.35.1 Detailed Description

Options for saving PNG images.

7.35.2 Constructor & Destructor Documentation

7.35.2.1 PngOption() [inline]

7.35.3 Property Documentation

7.35.3.1 unsigned int compressionLevel

Compression level (0-9).

0 is no compression, 9 is best compression.

7.35.3.2 bool interlaced

Whether to save the PNG as interlaced.

7.36 PpmOption Struct Reference

Options for saving PPM images.

Public Member Functions

• PpmOption ()

Properties

• bool binaryFile

Whether to save the PPM as a binary file.

7.36.1 Detailed Description

Options for saving PPM images.

7.36.2 Constructor & Destructor Documentation

7.36.2.1 PpmOption() [inline]

7.36.3 Property Documentation

7.36.3.1 bool binaryFile

Whether to save the PPM as a binary file.

7.37 StrobeControl Struct Reference

A camera strobe.

Properties

• unsigned int source *Source value.*

• bool onOff

Flag controlling on/off.

• unsigned int polarity

Signal polarity.

float delay

Signal delay (in ms).

• float duration

Signal duration (in ms).

7.37.1 Detailed Description

A camera strobe.

7.37.2 Property Documentation

7.37.2.1 float delay

Signal delay (in ms).

7.37.2.2 float duration

Signal duration (in ms).

7.37.2.3 **bool onOff**

Flag controlling on/off.

7.37.2.4 unsigned int polarity

Signal polarity.

7.37.2.5 unsigned int source

Source value.

7.38 StrobeInfo Struct Reference

A camera strobe property.

Properties

• unsigned int source

Source value.

• bool present

Presence of strobe.

• bool readOutSupported

Flag indicating if strobe value can be read out.

· bool onOffSupported

Flag indicating if on/off is supported.

• bool polaritySupported

Flag indicating if polarity is supported.

• float minValue

Minimum value.

• float maxValue

Maximum value.

7.38.1 Detailed Description

A camera strobe property.

7.38.2 Property Documentation

7.38.2.1 float maxValue

Maximum value.

7.38.2.2 float minValue

Minimum value.

7.38.2.3 bool onOffSupported

Flag indicating if on/off is supported.

7.38.2.4 bool polaritySupported

Flag indicating if polarity is supported.

7.38.2.5 bool present

Presence of strobe.

7.38.2.6 bool readOutSupported

Flag indicating if strobe value can be read out.

7.38.2.7 unsigned int source

Source value.

7.39 SystemInfo Struct Reference

Description of the system.

Properties

• OSType osType

Operating system type as described by OSType.

• System::String^ osDescription

Detailed description of the operating system.

• ByteOrder byteOrder

Byte order of the system.

unsigned int systemMemorySize
 Amount of memory available on the system.

• System::String cpuDescription

Detailed description of the CPU.

• unsigned int numCpuCores

Number of cores on all CPUs on the system.

• System::String^ driverList

List of drivers used.

• System::String^ libraryList

List of libraries used.

• System::String^ gpuDescription

Detailed description of the GPU.

• unsigned int screenWidth

Screen resolution width in pixels.

• unsigned int screenHeight

Screen resolution height in pixels.

7.39.1 Detailed Description

Description of the system.

7.39.2 Property Documentation

7.39.2.1 ByteOrder byteOrder

Byte order of the system.

7.39.2.2 System:: String^ cpuDescription

Detailed description of the CPU.

7.39.2.3 System:: String^{\(\)} driverList

List of drivers used.

7.39.2.4 System:: String\(^\) gpuDescription

Detailed description of the GPU.

7.39.2.5 System:: String^{\(\)} libraryList

List of libraries used.

7.39.2.6 unsigned int numCpuCores

Number of cores on all CPUs on the system.

7.39.2.7 System:: String\(^\) osDescription

Detailed description of the operating system.

7.39.2.8 OSType osType

Operating system type as described by OSType.

7.39.2.9 unsigned int screenHeight

Screen resolution height in pixels.

7.39.2.10 unsigned int screenWidth

Screen resolution width in pixels.

7.39.2.11 unsigned int systemMemorySize

Amount of memory available on the system.

7.40 TiffOption Struct Reference

Options for saving TIFF images.

Public Types

```
enum CompressionMethod {
None = 1,
PackBits,
Deflate,
AdobeDeflate,
CcittFax3,
CcittFax4,
Lzw,
Jpeg }
```

Public Member Functions

- TiffOption ()

Properties

- CompressionMethod compression

Compression method to use for encoding TIFF images.

7.40.1 Detailed Description

Options for saving TIFF images.

7.40.2 Member Enumeration Documentation

7.40.2.1 enum CompressionMethod

Enumerator:

None Save without any compression.

PackBits Save using PACKBITS compression.

Deflate Save using DEFLATE compression (ZLIB compression).

AdobeDeflate Save using ADOBE DEFLATE compression.

CcittFax3 Save using CCITT Group 3 fax encoding.

This is only valid for 1-bit images only. Default to LZW for other bit depths.

CcittFax4 Save using CCITT Group 4 fax encoding.

This is only valid for 1-bit images only. Default to LZW for other bit depths.

Lzw Save using LZW compression.

Jpeg Save using JPEG compression.

This is only valid for 8-bit greyscale and 24-bit only. Default to LZW for other bit depths.

7.40.3 Constructor & Destructor Documentation

7.40.3.1 TiffOption() [inline]

7.40.4 Property Documentation

7.40.4.1 CompressionMethod compression

Compression method to use for encoding TIFF images.

7.41 TimeStamp Struct Reference

Timestamp information.

Properties

- long long seconds
 Seconds.
- unsigned int microSeconds
 Microseconds.
- unsigned int cycleSeconds 1394 cycle time seconds.
- unsigned int cycleCount
 1394 cycle time count.
- unsigned int cycleOffset
 1394 cycle time offset.

7.41.1 Detailed Description

Timestamp information.

7.41.2 Property Documentation

7.41.2.1 unsigned int cycleCount

1394 cycle time count.

7.41.2.2 unsigned int cycleOffset

1394 cycle time offset.

7.41.2.3 unsigned int cycleSeconds

1394 cycle time seconds.

7.41.2.4 unsigned int microSeconds

Microseconds.

7.41.2.5 long long seconds

Seconds.

7.42 Translate Class Reference

Static Package Functions

```
    static ErrorType translate (FlyCapture2::ErrorType errorType)

    static FlyCapture2::ErrorType translate (ErrorType errorType)

    static GrabMode translate (FlyCapture2::GrabMode grabMode)

    static FlyCapture2::GrabMode translate (GrabMode grabMode)

  static BandwidthAllocation translate (FlyCapture2::BandwidthAllocation bandwidthAlloca-
- static FlyCapture2::BandwidthAllocation translate (BandwidthAllocation bandwidthAlloca-
  tion)

    static InterfaceType translate (FlyCapture2::InterfaceType interfaceType)

    static FlyCapture2::InterfaceType translate (InterfaceType interfaceType)

    static PropertyType translate (FlyCapture2::PropertyType propertyType)

  static FlyCapture2::PropertyType translate (PropertyType propertyType)
  static FrameRate translate (FlyCapture2::FrameRate frmRate)
- static FlyCapture2::FrameRate translate (FrameRate frmRate)

    static VideoMode translate (FlyCapture2::VideoMode videoMode)

    static FlyCapture2::VideoMode translate (VideoMode videoMode)

    static PixelFormat translate (FlyCapture2::PixelFormat pixelFormat)

    static FlyCapture2::PixelFormat translate (PixelFormat pixelFormat)

    static BayerTileFormat translate (FlyCapture2::BayerTileFormat bayerFormat)

    static FlyCapture2::BayerTileFormat translate (BayerTileFormat bayerFormat)

    static Mode translate (FlyCapture2::Mode mode)

    static FlyCapture2::Mode translate (Mode mode)

  static BusSpeed translate (FlyCapture2::BusSpeed busSpeed)

    static FlyCapture2::BusSpeed translate (BusSpeed busSpeed)

  static ColorProcessingAlgorithm translate (FlyCapture2::ColorProcessingAlgorithm algo-
  rithm)
- static FlyCapture2::ColorProcessingAlgorithm translate (ColorProcessingAlgorithm algo-
  rithm)
  static ImageFileFormat translate (FlyCapture2::ImageFileFormat fileFmt)
- static FlyCapture2::ImageFileFormat translate (ImageFileFormat fileFmt)
  static
                    TiffOption::CompressionMethod
                                                                 translate
                                                                                      (FlyCap-
  ture2::TIFFOption::CompressionMethod method)
               FlyCapture2::TIFFOption::CompressionMethod
static
                                                                      translate
                                                                                       (TiffOp-
  tion::CompressionMethod method)

    static StatisticsChannel translate (FlyCapture2::ImageStatistics::StatisticsChannel channel)

    static FlyCapture2::ImageStatistics::StatisticsChannel translate (StatisticsChannel channel)

    static OSType translate (FlyCapture2::OSType osType)

  static FlyCapture2::OSType translate (OSType osType)

    static ByteOrder translate (FlyCapture2::ByteOrder byteOrder)

    static FlyCapture2::ByteOrder translate (ByteOrder byteOrder)

    static GigEPropertyType translate (FlyCapture2::GigEPropertyType propType)

  static FlyCapture2::GigEPropertyType translate (GigEPropertyType propType)
  static void ToMgd (FlyCapture2::FC2Config *pNative, FC2Config^ mgd)
  static void ToNative (FC2Config^ mgd, FlyCapture2::FC2Config *pNative)
- static void ToMgd (FlyCapture2::PropertyInfo *pNative, CameraPropertyInfo^ mgd)
- static void ToNative (CameraPropertyInfo^ mgd, FlyCapture2::PropertyInfo *pNative)
- static void ToMgd (FlyCapture2::Property *pNative, CameraProperty^ mgd)
- static void ToNative (CameraProperty\(^\) mgd, FlyCapture2::Property \(^\)*pNative)

    static void ToMgd (FlyCapture2::TriggerModeInfo *pNative, TriggerModeInfo^ mgd)

    static void ToNative (TriggerModeInfo^ mgd, FlyCapture2::TriggerModeInfo *pNative)

    static void ToMgd (FlyCapture2::TriggerMode *pNative, TriggerMode mgd)

    static void ToNative (TriggerMode<sup>^</sup> mgd, FlyCapture2::TriggerMode *pNative)

    static void ToMgd (FlyCapture2::StrobeInfo *pNative, StrobeInfo<sup>∧</sup> mgd)
```

static void ToNative (StrobeInfo[∧] mgd, FlyCapture2::StrobeInfo *pNative)

```
    static void ToMgd (FlyCapture2::StrobeControl *pNative, StrobeControl^ mgd)

    static void ToNative (StrobeControl<sup>∧</sup> mgd, FlyCapture2::StrobeControl *pNative)

    static void ToMgd (FlyCapture2::Format7ImageSettings *pNative, Format7ImageSettings^

    static void ToNative (Format7ImageSettings<sup>^</sup> mgd, FlyCapture2::Format7ImageSettings

  *pNative)

    static void ToMgd (FlyCapture2::Format7Info *pNative, Format7Info<sup>∧</sup> mgd)

    static void ToNative (Format7Info<sup>↑</sup> mgd, FlyCapture2::Format7Info *pNative)

  static void ToMgd (FlyCapture2::Format7PacketInfo *pNative, Format7PacketInfo^ mgd)

    static void ToNative (Format7PacketInfo^ mgd, FlyCapture2::Format7PacketInfo *pNative)

    static void ToMgd (FlyCapture2::TimeStamp *pNative, TimeStamp<sup>∧</sup> mgd)

    static void ToNative (TimeStamp^ mgd, FlyCapture2::TimeStamp *pNative)

    static void ToMgd (FlyCapture2::ConfigROM *pNative, ConfigROM<sup>∧</sup> mgd)

    static void ToNative (ConfigROM<sup>^</sup> mgd, FlyCapture2::ConfigROM *pNative)

    static void ToMgd (FlyCapture2::CameraInfo *pNative, CameraInfo<sup>∧</sup> mgd)

    static void ToNative (CameraInfo<sup>∧</sup> mgd, FlyCapture2::CameraInfo *pNative)

  static void ToMgd (FlyCapture2::ImageMetadata *pNative, ImageMetadata^ mgd)

    static void ToNative (ImageMetadata mgd, FlyCapture2::ImageMetadata *pNative)
    static void ToMgd (FlyCapture2::LUTData *pNative, LutData mgd)

    static void ToNative (LutData^ mgd, FlyCapture2::LUTData *pNative)

- static void ToMgd (FlyCapture2::EmbeddedImageInfoProperty *pNative, EmbeddedImageIn-
  foProperty<sup>∧</sup> mgd)
  static
              void
                        ToNative
                                        (EmbeddedImageInfoProperty^
                                                                              mgd,
                                                                                           FlyCap-
  ture2::EmbeddedImageInfoProperty *pNative)
  static void ToMgd (FlyCapture2::EmbeddedImageInfo *pNative, EmbeddedImageInfo^ mgd)
  static void ToNative (EmbeddedImageInfo^ mgd, FlyCapture2::EmbeddedImageInfo
  static void ToMgd (FlyCapture2::PNGOption *pNative, PngOption \(^{\text{Mgd}}\) mgd)
- static void ToNative (PngOption<sup>∧</sup> mgd, FlyCapture2::PNGOption *pNative)

    static void ToMgd (FlyCapture2::PPMOption *pNative, PpmOption ↑ mgd)

    static void ToNative (PpmOption<sup>↑</sup> mgd, FlyCapture2::PPMOption *pNative)

    static void ToMgd (FlyCapture2::PGMOption *pNative, PgmOption<sup>∧</sup> mgd)

    static void ToNative (PgmOption<sup>^</sup> mgd, FlyCapture2::PGMOption *pNative)

    static void ToMgd (FlyCapture2::TIFFOption *pNative, TiffOption<sup>∧</sup> mgd)

    static void ToNative (TiffOption<sup>^</sup> mgd, FlyCapture2::TIFFOption *pNative)

    static void ToMgd (FlyCapture2::JPEGOption *pNative, JpegOption<sup>∧</sup> mgd)

    static void ToNative (JpegOption<sup>^</sup> mgd, FlyCapture2::JPEGOption *pNative)

    static void ToMgd (FlyCapture2::JPG2Option *pNative, Jpg2Option^ mgd)

    static void ToNative (Jpg2Option<sup>∧</sup> mgd, FlyCapture2::JPG2Option *pNative)

    static void ToNative (AviOption<sup>∧</sup> mgd, FlyCapture2::AVIOption *pNative)

  static void ToMgd (FlyCapture2::SystemInfo *pNative, SystemInfo<sup>∧</sup> mgd)

    static void ToMgd (FlyCapture2::FC2Version *pNative, FC2Version^ mgd)

  static void ToMgd (FlyCapture2::IPAddress *pNative, System::Net::IPAddress^ %mgd)
  static void ToNative (System::Net::IPAddress * mgd, FlyCapture2::IPAddress *pNative)
                                                  (FlyCapture2::MACAddress
                  void
                                ToMgd
                                                                                          *pNative,
  System::Net::NetworkInformation::PhysicalAddress^ %mgd)
  static void ToNative (System::Net::NetworkInformation::PhysicalAddress<sup>^</sup> mgd, FlyCap-
  ture2::MACAddress *pNative)
  static void ToMgd (FlyCapture2::GigEProperty *pNative, GigEProperty^ mgd)
  static void ToNative (GigEProperty \(^\) mgd, FlyCapture2::GigEProperty \(^\)*pNative)
  static void ToMgd (FlyCapture2::GigEImageSettingsInfo *pNative, GigEImageSettingsInfo^
```

static void ToNative (GigEImageSettingsInfo[^] mgd, FlyCapture2::GigEImageSettingsInfo

static void ToMgd (FlyCapture2::GigEImageSettings *pNative, GigEImageSettings^ mgd)
 static void ToNative (GigEImageSettings^ mgd, FlyCapture2::GigEImageSettings *pNative)
 static void ToMgd (FlyCapture2::GigEStreamChannel *pNative, GigEStreamChannel^ mgd)
 static void ToNative (GigEStreamChannel^ mgd, FlyCapture2::GigEStreamChannel *pNative)

mgd)

*pNative)

7.42.1 Member Function Documentation

- **7.42.1.1 void ToMgd (FlyCapture2::GigEStreamChannel*** *pNative*, **GigEStreamChannel**^ *mgd*) [static, package]
- 7.42.1.2 void ToMgd (FlyCapture2::GigEImageSettings * pNative, GigEImageSettings $^{\wedge}$ mgd) [static, package]
- 7.42.1.3 void ToMgd (FlyCapture2::GigEImageSettingsInfo * pNative, GigEImageSettingsInfo^mgd) [static, package]
- **7.42.1.4 void ToMgd (FlyCapture2::GigEProperty** * *pNative*, **GigEProperty**^ *mgd*) [static, package]
- 7.42.1.5 void ToMgd (FlyCapture2::MACAddress * pNative,
 System::Net::NetworkInformation::PhysicalAddress^ % mgd) [static, package]
- **7.42.1.6 void ToMgd (FlyCapture2::IPAddress** * *pNative*, System::Net::IPAddress^ % *mgd*) [static, package]
- **7.42.1.7 void ToMgd (FlyCapture2::FC2Version** * pNative, FC2Version $^{\wedge}$ mgd) [static, package]
- **7.42.1.8 void ToMgd (FlyCapture2::SystemInfo * pNative, SystemInfo ^{\wedge} mgd)** [static, package]
- **7.42.1.9 void ToMgd (FlyCapture2::JPG2Option** * *pNative*, **Jpg2Option** $^{\wedge}$ *mgd*) [static, package]
- **7.42.1.10 void ToMgd (FlyCapture2::JPEGOption** * *pNative*, **JpegOption**^ *mgd*) [static, package]
- **7.42.1.11 void ToMgd (FlyCapture2::TIFFOption** *pNative, **TiffOption** $^{\wedge}$ mgd) [static, package]
- **7.42.1.12 void ToMgd (FlyCapture2::PGMOption** * *pNative*, **PgmOption**^ *mgd*) [static, package]
- **7.42.1.13 void ToMgd (FlyCapture2::PPMOption** * *pNative*, **PpmOption** ^ *mgd*) [static, package]
- **7.42.1.14** void ToMgd (FlyCapture2::PNGOption * pNative, PngOption $^{\wedge}$ mgd) [static, package]
- 7.42.1.15 void ToMgd (FlyCapture2::EmbeddedImageInfo * pNative, EmbeddedImageInfo $^{\wedge}$ mgd) [static, package]
- **7.42.1.16 void ToMgd (FlyCapture2::EmbeddedImageInfoProperty** * *pNative*, **EmbeddedImageInfoProperty**^ *mgd*) [static, package]
- **7.42.1.17** void ToMgd (FlyCapture2::LUTData * pNative, LutData $^{\wedge}$ mgd) [static, package]
- 7.42.1.18 void ToMgd (FlyCapture2::ImageMetadata * pNative, ImageMetadata $^{\wedge}$ mgd) [static, package]
- **7.42.1.19 void ToMgd (FlyCapture2::CameraInfo** * *pNative*, **CameraInfo**^ *mgd*) [static, package]
- Generate 42 The 20p 7 white 5 Tawled (Figure three 2p: Config ROM * pNative, Config ROM ^ mgd) [static, package]
 - **7.42.1.21 void ToMgd (FlyCapture2::TimeStamp** * pNative, **TimeStamp** $^{\wedge}$ mgd) [static, package]
 - 7.42.1.22 void ToMgd (FlyCapture2::Format7PacketInfo * pNative, Format7PacketInfo^

7.43 TriggerMode Struct Reference

A camera trigger.

Properties

- bool onOff

Flag controlling on/off.

- unsigned int polarity
 Polarity value.
- unsigned int source *Source value.*
- unsigned int mode
 Mode value.
- unsigned int parameter
 Parameter value.

7.43.1 Detailed Description

A camera trigger.

7.43.2 Property Documentation

7.43.2.1 unsigned int mode

Mode value.

7.43.2.2 **bool onOff**

Flag controlling on/off.

7.43.2.3 unsigned int parameter

Parameter value.

7.43.2.4 unsigned int polarity

Polarity value.

7.43.2.5 unsigned int source

Source value.

7.44 TriggerModeInfo Struct Reference

Information about a camera trigger property.

Properties

bool present

Presence of trigger mode.

- bool readOutSupported

Flag indicating if trigger value can be read out.

- bool onOffSupported

Flag indicating if on/off is supported.

- bool polaritySupported

Flag indicating if polarity is supported.

bool valueReadable

Flag indicating if the value is readable.

- unsigned int sourceMask

Source mask.

- bool softwareTriggerSupported

Flag indicating if software trigger is supported.

- unsigned int modeMask

Mode mask.

7.44.1 Detailed Description

Information about a camera trigger property.

7.44.2 Property Documentation

7.44.2.1 unsigned int modeMask

Mode mask.

7.44.2.2 bool on Off Supported

Flag indicating if on/off is supported.

7.44.2.3 bool polaritySupported

Flag indicating if polarity is supported.

7.44.2.4 bool present

Presence of trigger mode.

7.44.2.5 bool readOutSupported

Flag indicating if trigger value can be read out.

7.44.2.6 bool softwareTriggerSupported

Flag indicating if software trigger is supported.

7.44.2.7 unsigned int sourceMask

Source mask.

7.44.2.8 bool valueReadable

Flag indicating if the value is readable.

Index

~CameraControlDialog	available
FlyCapture2Managed::Gui::CameraControlDialo	og, 42FlyCapture2Managed::EmbeddedImageInfoProperty, 57
~CameraSelectionDialog	AVIAppend
FlyCapture2Managed::Gui::CameraSelectionDia	llog, ½ lyCapture2Managed::ManagedAVIRecorder, 83
~FC2Exception	AVIClose
FlyCapture2Managed::FC2Exception, 61	FlyCapture2Managed::ManagedAVIRecorder, 83
~ManagedAVIRecorder	AVIOpen
FlyCapture2Managed::ManagedAVIRecorder, 83	FlyCapture2Managed::ManagedAVIRecorder, 83
~ManagedBusManager	AviOption
FlyCapture2Managed::ManagedBusManager, 87	FlyCapture2Managed::AviOption, 41
~ManagedCamera	
FlyCapture2Managed::ManagedCamera, 94	BandwidthAllocation
~ManagedCameraBase	Enumerations, 15
FlyCapture2Managed::ManagedCameraBase, 10	bandwidthAllocation
~ManagedGigECamera	FlyCapture2Managed::FC2Config, 58
FlyCapture2Managed::ManagedGigECamera, 11	B ayerTileFormat
~ManagedImage	Enumerations, 16
FlyCapture2Managed::ManagedImage, 125	bayerTileFormat
~ManagedImageStatistics	FlyCapture2Managed::CameraInfo, 44
FlyCapture2Managed::ManagedImageStatistics,	131 FlyCapture2Managed::ManagedImage, 128
	BGGR
absControl	Enumerations, 16
FlyCapture2Managed::CameraProperty, 48	BigEndian
absMax	Enumerations, 17
FlyCapture2Managed::CameraPropertyInfo, 50	binaryFile
absMin	FlyCapture2Managed::PgmOption, 135
FlyCapture2Managed::CameraPropertyInfo, 50	FlyCapture2Managed::PpmOption, 137
absValSupported	bitmap
FlyCapture2Managed::CameraPropertyInfo, 50	FlyCapture2Managed::ManagedImage, 128
absValue	bitsPerPixel
FlyCapture2Managed::CameraProperty, 48	FlyCapture2Managed::ManagedImage, 128
AdobeDeflate	Blue
FlyCapture2Managed::TiffOption, 143	Enumerations, 23
Any	Bmp
Enumerations, 16	Enumerations, 20
Arrival	Brightness
Enumerations, 20	Enumerations, 22
asyncBusSpeed	brightness
FlyCapture2Managed::FC2Config, 58	FlyCapture2Managed::EmbeddedImageInfo, 56
AutoExposure	BufferFrames
Enumerations, 22	Enumerations, 19
autoManualMode	BufferTooSmall
FlyCapture2Managed::CameraProperty, 48	Enumerations, 18
autoSupported	build
FlyCapture2Managed::CameraPropertyInfo, 50	FlyCapture2Managed::FC2Version, 62

154 INDEX

BusMasterFailed	ConvertToNativeGuid
Enumerations, 18	FlyCapture2Managed::ManagedBusManager, 87
BusReset	cpuDescription
Enumerations, 20	FlyCapture2Managed::SystemInfo, 141
BusSpeed	cycleCount
Enumerations, 16	FlyCapture2Managed::TimeStamp, 145
ByteOrder	cycleOffset
Enumerations, 16	FlyCapture2Managed::TimeStamp, 145
byteOrder	cycleSeconds
FlyCapture2Managed::SystemInfo, 141	FlyCapture2Managed::TimeStamp, 145
CalculateStatistics	data
FlyCapture2Managed::ManagedImage, 125	FlyCapture2Managed::ManagedImage, 129
CameraControlDialog	Default
FlyCapture2Managed::Gui::CameraControlDiale	og, 42Enumerations, 17
CameraProperty	defaultColorProcessingAlgorithm
FlyCapture2Managed::CameraProperty, 48	FlyCapture2Managed::ManagedImage, 129
CameraPropertyInfo	defaultGateway
FlyCapture2Managed::CameraPropertyInfo, 50	FlyCapture2Managed::CameraInfo, 44
CameraSelectionDialog	defaultOutputPixelFormat
	alog, PlyCapture2Managed::ManagedImage, 129
CauseType	Deflate
FlyCapture2Managed::FC2Exception, 61	FlyCapture2Managed::TiffOption, 143
CcittFax3	delay
FlyCapture2Managed::TiffOption, 143	FlyCapture2Managed::StrobeControl, 138
CcittFax4	destinationIpAddress
FlyCapture2Managed::TiffOption, 143	FlyCapture2Managed::GigEStreamChannel, 75
channels	DetermineBitsPerPixel
FlyCapture2Managed::GigEConfig, 69	
chipIdHi	FlyCapture2Managed::ManagedImage, 126 DisableAll
FlyCapture2Managed::ConfigROM, 53	FlyCapture2Managed::ManagedImageStatistics, 131
chipIdLo	Disconnect
FlyCapture2Managed::ConfigROM, 53	FlyCapture2Managed::Gui::CameraControlDialog, 42
ColorProcessingAlgorithm	
Enumerations, 17	FlyCapture2Managed::ManagedCameraBase, 101 DiscoverGigECameras
colorProcessingAlgorithm	e e e e e e e e e e e e e e e e e e e
FlyCapture2Managed::ManagedImage, 128	FlyCapture2Managed::ManagedBusManager, 87
	DiscoverGigEPacketSize
cols FlyCapture2Managed::ManagedImage, 129	FlyCapture2Managed::ManagedGigECamera, 117
	doNotFragment
compression ElyContinue 2 Managed w Tiff Ontion 144	FlyCapture2Managed::GigEStreamChannel, 75
FlyCapture2Managed::TiffOption, 144 compressionLevel	driverList
1	FlyCapture2Managed::SystemInfo, 142
FlyCapture2Managed::PngOption, 136	driverName
CompressionMethod	FlyCapture2Managed::CameraInfo, 44
FlyCapture2Managed::TiffOption, 143	DropFrames
configROM	Enumerations, 19
FlyCapture2Managed::CameraInfo, 44	duration
Connect	FlyCapture2Managed::StrobeControl, 138
FlyCapture2Managed::Gui::CameraControlDial	•
FlyCapture2Managed::ManagedCameraBase, 10	•
Convert	Enumerations, 17
FlyCapture2Managed::ManagedImage, 125	embeddedBrightness
ConvertToManagedGuid	FlyCapture2Managed::ImageMetadata, 77
FlyCapture2Managed::ManagedBusManager, 8'	/ embeddedExposure

INDEX 155

FlyCapture2Managed::ImageMetadata, 77	ErrorType, 17
embeddedFrameCounter	Failed, 17
FlyCapture2Managed::ImageMetadata, 78	FailedBusMasterConnection, 17
embeddedGain	FailedGuid, 17
FlyCapture2Managed::ImageMetadata, 78	Fastest, 16
embeddedGPIOPinState	Focus, 23
FlyCapture2Managed::ImageMetadata, 78	FrameRate, 18, 23
EmbeddedImageInfo	FrameRate120, 18
FlyCapture2Managed::EmbeddedImageInfo, 56	FrameRate15, 18
embeddedROIPosition	FrameRate1_875, 18
FlyCapture2Managed::ImageMetadata, 78	FrameRate240, 18
embeddedShutter	FrameRate30, 18
FlyCapture2Managed::ImageMetadata, 78	FrameRate3_75, 18
embeddedStrobePattern	FrameRate60, 18
FlyCapture2Managed::ImageMetadata, 78	FrameRate7_5, 18
embeddedTimeStamp	FrameRateFormat7, 18
FlyCapture2Managed::ImageMetadata, 78	FromFileExtension, 20
embeddedWhiteBalance	Gain, 23
FlyCapture2Managed::ImageMetadata, 78	Gamma, 23
EnableAll	GBRG, 16
FlyCapture2Managed::ManagedImageStatistics, 131	GigE, 20
enabled	GigE_10000Base_T, 16
FlyCapture2Managed::LutData, 81	GigE_1000Base_T, 16
EnableGreyOnly	GigE_100Base_T, 16
FlyCapture2Managed::ManagedImageStatistics, 131	GigE_10Base_T, 16
EnableHSLOnly	GigEPropertyType, 18
FlyCapture2Managed::ManagedImageStatistics, 131	GrabMode, 19
EnableLUT	GrabTimeout, 19
FlyCapture2Managed::ManagedCameraBase, 101	GRBG, 16
EnableRGBOnly	Green, 23
FlyCapture2Managed::ManagedImageStatistics, 131	Grey, 23
EnumCallback	HeartbearTimeout, 19
FlyCapture2Managed, 39	Heartbeat, 19
Enumerations, 9	HQLinear, 17
Any, 16	Hue, 23
Arrival, 20	Ieee1394, 20
AutoExposure, 22	IidcFailed, 18
BandwidthAllocation, 15	ImageConsistencyError, 18
BayerTileFormat, 16	ImageConversionFailed, 18
BGGR, 16	ImageFileFormat, 20
BigEndian, 17	ImageLibraryFailure, 18
Blue, 23	Infinite, 19
Bmp, 20	InitFailed, 17
Brightness, 22	InterfaceType, 20
BufferFrames, 19	InvalidBuManager, 17
BufferTooSmall, 18	InvalidGeneration, 18
BusMasterFailed, 18	InvalidMode, 18
BusReset, 20	InvalidPacketSize, 18
BusSpeed, 16	InvalidParameter, 17
ByteOrder, 16	InvalidSettings, 17
ColorProcessingAlgorithm, 17	Iris, 23
Default, 17	IsochAlreadyStarted, 18
DropFrames, 19	IsochBandwidthExceeded, 18
EdgeSensing, 17	IsochFailed, 18

156 INDEX

IsochNotStarted, 18	NotImplemented, 17
IsochRetrieveBufferFailed, 18	NotInFormat7, 18
IsochStartFailed, 18	NotInitialized, 17
IsochStopFailed, 18	NotSupported, 18
IsochSyncFailed, 18	NumberOfFrameRates, 18
Jpeg, 20	NumberOfModes, 21
Jpeg2000, 20	NumberOfPixelFormats, 22
Lightness, 23	NumberOfStatisticsChannels, 23
LinuxX64, 22	NumberOfVideoModes, 24
LinuxX86, 22	Off, 16
LittleEndian, 17	Ok, 17
LowLevelFailure, 17	On, 16
LutFailed, 18	OSType, 21
Mac, 22	PacketDelay, 19
ManagedCallbackType, 20	PacketSize, 19
Memory Allocation Failed, 17	Pan, 23
Mode, 20	Pgm, 20
Mode0, 21	PixelFormat, 22
Mode1, 21	PixelFormat411Yuv8, 22
Mode 10, 21	PixelFormat422Yuv8, 22
Mode11, 21	PixelFormat444Yuv8, 22
Mode12, 21	PixelFormatBgr, 22
Mode13, 21	PixelFormatBgru, 22
Mode 14, 21	PixelFormatMono12, 22
Mode 15, 21	PixelFormatMono16, 22
Mode 16, 21	PixelFormatMono8, 22
Mode 17, 21	PixelFormatRaw12, 22
Mode 18, 21	PixelFormatRaw16, 22
Mode 19, 21	PixelFormatRaw8, 22
Mode2, 21	PixelFormatRgb, 22
Mode20, 21	PixelFormatRgb16, 22
Mode21, 21	PixelFormatRgb8, 22
Mode22, 21	PixelFormatRgbu, 22
Mode23, 21	PixelFormatSignedMono16, 22
Mode24, 21	PixelFormatSignedRgb16, 22
Mode25, 21	Png, 20
Mode26, 21	Ppm, 20
Mode27, 21	PropertyFailed, 18
Mode28, 21	PropertyNotPresent, 18
Mode29, 21	PropertyType, 22
Mode3, 21 Mode3, 21	Raw, 20
Mode30, 21	ReadRegisterFailed, 18
Mode31, 21	Red, 23
Mode4, 21	RegisterFailed, 18
	Removal, 20
Mode5, 21	
Mode6, 21	RGGB, 16
Mode7, 21	Rigorous, 17
Mode8, 21	\$100, 16
Mode9, 21	S1600, 16
NearestNeighbor, 17	S200, 16
NoColorProcessing, 17	S3200, 16
None, 16, 19	\$400, 16
NotConnected, 17	S480, 16
NotFound, 17	S800, 16

Saturation, 23	Failed
Sharpness, 23	Enumerations, 17
Shutter, 23	FailedBusMasterConnection
StatisticsChannel, 23	Enumerations, 17
StrobeFailed, 18	FailedGuid
Temperature, 23	Enumerations, 17
Tiff, 20	Fastest
Tilt, 23	Enumerations, 16
Timeout, 18	FC2Config
TriggerDelay, 23	FlyCapture2Managed::FC2Config, 58
TriggerFailed, 18	FC2Exception
TriggerMode, 23	FlyCapture2Managed::FC2Exception, 61
Undefined, 17	FireBusReset
Unknown, 16, 20	FlyCapture2Managed::ManagedBusManager, 87
UnknownOS, 22	FireSoftwareTrigger
Unspecified, 16, 19, 23	FlyCapture2Managed::ManagedCameraBase, 10
Unsupported, 16	firmwareBuildTime
Usb2, 20	FlyCapture2Managed::CameraInfo, 45
VideoMode, 23	firmwareVersion
VideoMode1024x768Rgb, 24	FlyCapture2Managed::CameraInfo, 45
VideoMode1024x768Y16, 24	FlyCapture2, 29
VideoMode1024x768116, 24 VideoMode1024x768Y8, 24	FlyCapture2Managed, 30
VideoMode1024x768Yuv422, 24	EnumCallback, 39
VideoMode1280x960Rgb, 24	ImageCallbackDelegate, 39
VideoMode1280x960Y16, 24	ImageEventCallback, 39
	FlyCapture2Managed::AviOption, 41
VideoMode1280x960Y8, 24	• • •
VideoMode1280x960Yuv422, 24	AviOption, 41
VideoMode1600x1200Rgb, 24	frameRate, 41
VideoMode1600x1200Y16, 24	FlyCapture2Managed::CameraInfo, 43
VideoMode1600x1200Y8, 24	bayerTileFormat, 44
VideoMode1600x1200Yuv422, 24	configROM, 44
VideoMode160x120Yuv444, 24	defaultGateway, 44
VideoMode320x240Yuv422, 24	driverName, 44
VideoMode640x480Rgb, 24	firmwareBuildTime, 45
VideoMode640x480Y16, 24	firmwareVersion, 45
VideoMode640x480Y8, 24	gigEMajorVersion, 45
VideoMode640x480Yuv411, 24	gigEMinorVersion, 45
VideoMode640x480Yuv422, 24	iidc Version, 45
VideoMode800x600Rgb, 24	interfaceType, 45
VideoMode800x600Y16, 24	ipAddress, 45
VideoMode800x600Y8, 24	isColorCamera, 45
VideoMode800x600Yuv422, 24	macAddress, 45
VideoModeFormat7, 24	maximumBusSpeed, 45
WhiteBalance, 23	modelName, 45
WindowsX64, 22	sensorInfo, 46
WindowsX86, 22	sensorResolution, 46
WriteRegisterFailed, 18	serialNumber, 46
Zoom, 23	subnetMask, 46
Equals	userDefinedName, 46
FlyCapture2Managed::ManagedPGRGuid, 133	vendorName, 46
ErrorType	xmlURL1, 46
Enumerations, 17	xmlURL2, 46
exposure	FlyCapture2Managed::CameraProperty, 47
FlyCapture2Managed::EmbeddedImageInfo, 56	absControl, 48

absValue, 48	bandwidthAllocation, 58
autoManualMode, 48	FC2Config, 58
CameraProperty, 48	grabMode, 59
onePush, 48	grabTimeout, 59
onOff, 48	isochBusSpeed, 59
present, 48	numBuffers, 59
type, 48	numImageNotifications, 59
valueA, 48	FlyCapture2Managed::FC2Exception, 60
valueB, 48	~FC2Exception, 61
FlyCapture2Managed::CameraPropertyInfo, 49	CauseType, 61
absMax, 50	FC2Exception, 61
absMin, 50	Type, 61
absValSupported, 50	FlyCapture2Managed::FC2Version, 62
autoSupported, 50	build, 62
CameraPropertyInfo, 50	major, 62
manualSupported, 50	minor, 62
max, 50	type, 62
min, 50	FlyCapture2Managed::Format7ImageSettings, 63
onePushSupported, 50	height, 63
onOffSupported, 51	mode, 63
present, 51	offsetX, 63
readOutSupported, 51	offsetY, 63
type, 51	pixelFormat, 63
unitAbbr, 51	width, 64
units, 51	FlyCapture2Managed::Format7Info, 65
FlyCapture2Managed::ConfigROM, 53	imageHStepSize, 66
chipIdHi, 53	imageVStepSize, 66
chipIdLo, 53	maxHeight, 66
keyword, 54	maxPacketSize, 66
nodeVendorId, 54	maxWidth, 66
unitSpecId, 54	minPacketSize, 66
unitSubSWVer, 54	mode, 66
unitSWVer, 54	offsetHStepSize, 66
vendorUniqueInfo0, 54	<u>*</u>
* ·	offsetVStepSize, 66
vendorUniqueInfo1, 54	packetSize, 66
vendorUniqueInfo2, 54	percentage, 66
vendorUniqueInfo3, 54	pixelFormatBitField, 66
FlyCapture2Managed::EmbeddedImageInfo, 55	FlyCapture2Managed::Format7PacketInfo, 68
brightness, 56	maxBytesPerPacket, 68
EmbeddedImageInfo, 56	recommendedBytesPerPacket, 68
exposure, 56	unitBytesPerPacket, 68
frameCounter, 56	FlyCapture2Managed::GigEConfig, 69
gain, 56	channels, 69
GPIOPinState, 56	numChannels, 69
ROIPosition, 56	FlyCapture2Managed::GigEImageSettings, 70
shutter, 56	height, 70
strobePattern, 56	offsetX, 70
timestamp, 56	offsetY, 70
whiteBalance, 56	pixelFormat, 70
Fly Capture 2 Managed:: Embedded Image Info Property,	
available, 57	FlyCapture2Managed::GigEImageSettingsInfo, 71
onOff, 57	imageHStepSize, 71
FlyCapture2Managed::FC2Config, 58	imageVStepSize, 71
asyncBusSpeed, 58	maxHeight, 71

maxWidth, 71	numBanks, 81
offsetHStepSize, 72	numChannels, 81
offsetVStepSize, 72	numEntries, 82
pixelFormatBitField, 72	outputBitDepth, 82
FlyCapture2Managed::GigEProperty, 73	supported, 82
isReadable, 73	FlyCapture2Managed::ManagedAVIRecorder, 83
isWritable, 73	~ManagedAVIRecorder, 83
max, 73	AVIAppend, 83
min, 73	AVIClose, 83
propType, 73	AVIOpen, 83
value, 74	ManagedAVIRecorder, 83
FlyCapture2Managed::GigEStreamChannel, 75	FlyCapture2Managed::ManagedBusManager, 85
destinationIpAddress, 75	~ManagedBusManager, 87
doNotFragment, 75	ConvertToManagedGuid, 87
hostPost, 75	ConvertToNativeGuid, 87
interPacketDelay, 75	DiscoverGigECameras, 87
networkInterfaceIndex, 76	FireBusReset, 87
packetSize, 76	ForceIPAddressToCamera, 87
sourcePort, 76	GetCameraFromIndex, 88
FlyCapture2Managed::Gui, 40	GetCameraFromIPAddress, 88
FlyCapture2Managed::Gui::CameraControlDialog, 42	
~CameraControlDialog, 42	GetCameraSerialNumberFromIndex, 89
CameraControlDialog, 42	GetDeviceFromIndex, 89
Connect, 42	GetInterfaceTypeFromGuid, 89
Disconnect, 42	GetNumOfCameras, 89
Hide, 42	GetNumOfDevices, 90
IsVisible, 42	ManagedBusManager, 87
Show, 42	ReadPhyRegister, 90
FlyCapture2Managed::Gui::CameraSelectionDialog,	
~CameraSelectionDialog, 52	RescanBus, 90
CameraSelectionDialog, 52	UnregisterCallback, 91
GetSelectedCameraGuids, 52	WritePhyRegister, 91
ShowModal, 52	FlyCapture2Managed::ManagedCamera, 92
FlyCapture2Managed::ImageMetadata, 77	~ManagedCamera, 94
	•
embeddedBrightness, 77	GetFormat7Info 04
embeddedExposure, 77	GetVideoMede And Frame Peter 04
embeddedFrameCounter, 78	GetVideoModeAndFrameRate, 94
embeddedGain, 78	GetVideoModeAndFrameRateInfo, 95
embeddedGPIOPinState, 78	ManagedCamera, 94
embeddedROIPosition, 78	SetFormat7Configuration, 95
embeddedShutter, 78	SetVideoModeAndFrameRate, 96
embeddedStrobePattern, 78	ValidateFormat7Settings, 96
embeddedTimeStamp, 78	FlyCapture2Managed::ManagedCameraBase, 97
embeddedWhiteBalance, 78	~ManagedCameraBase, 101
FlyCapture2Managed::JpegOption, 79	Connect, 101
JpegOption, 79	Disconnect, 101
progressive, 79	EnableLUT, 101
quality, 79	FireSoftwareTrigger, 101
FlyCapture2Managed::Jpg2Option, 80	GetActiveLUTBank, 101
Jpg2Option, 80	GetCameraInfo, 102
quality, 80	GetConfiguration, 102
FlyCapture2Managed::LutData, 81	GetEmbeddedImageInfo, 102
enabled, 81	GetGPIOPinDirection, 102
inputBitDepth, 81	GetLUTBankInfo, 103

GetLUTChannel, 103	SetGigEProperty, 120
GetLUTInfo, 103	SetGigEStreamChannelInfo, 120
GetMemoryChannel, 103	WriteGVCPMemory, 120
GetMemoryChannelInfo, 104	WriteGVCPRegister, 120
GetNativeCamera, 104	WriteGVCPRegisterBlock, 121
GetProperty, 104	FlyCapture2Managed::ManagedImage, 122
GetPropertyInfo, 104	∼ManagedImage, 125
GetStrobe, 105	bayerTileFormat, 128
GetStrobeInfo, 105	bitmap, 128
GetTriggerMode, 105	bitsPerPixel, 128
GetTriggerModeInfo, 106	CalculateStatistics, 125
IsConnected, 106	colorProcessingAlgorithm, 128
m_externalDelegate, 113	cols, 129
m_internalDelegate, 113	Convert, 125
m_pNativeCamBase, 113	data, 129
ManagedCameraBase, 101	defaultColorProcessingAlgorithm, 129
OnNativeCallback, 106	defaultOutputPixelFormat, 129
ReadRegister, 106	DetermineBitsPerPixel, 126
ReadRegisterBlock, 106	GetNativeImage, 126
RestoreFromMemoryChannel, 107	GetRawNativeImagePointer, 126
RetrieveBuffer, 107	imageMetadata, 129
SaveToMemoryChannel, 107	IsNativeImageValid, 126
SetActiveLUTBank, 108	ManagedImage, 125
SetCallback, 108	pixelFormat, 129
SetConfiguration, 108	ReleaseBuffer, 126
•	
SetEmbeddedImageInfo, 108	rows, 129
SetGPIOPinDirection, 109	Save, 126, 127
SetLUTChannel, 109	SetData, 128
SetProperty, 110	SetDimensions, 128
SetStrobe, 110	stride, 129
SetTriggerMode, 111	timeStamp, 129
StartCapture, 111	FlyCapture2Managed::ManagedImageStatistics, 130
StopCapture, 111	~ManagedImageStatistics, 131
WaitForBufferEvent, 112	DisableAll, 131
WriteRegister, 112	EnableAll, 131
WriteRegisterBlock, 112	EnableGreyOnly, 131
FlyCapture2Managed::ManagedGigECamera, 114	EnableHSLOnly, 131
~ManagedGigECamera, 117	EnableRGBOnly, 131
DiscoverGigEPacketSize, 117	GetChannelStatus, 131
GetGigEImageBinningSettings, 117	GetHistogram, 131
GetGigEImageSettings, 117	GetMean, 131
GetGigEImageSettingsInfo, 117	GetNativeImageStatistics, 131
GetGigEImagingMode, 117	GetNumPixelValues, 131
GetGigEProperty, 118	GetPixelValueRange, 131
GetGigEStreamChannelInfo, 118	GetRange, 131
GetNumStreamChannels, 118	GetStatistics, 131
ManagedGigECamera, 117	ManagedImageStatistics, 131
QueryGigEImagingMode, 118	SetChannelStatus, 131
ReadGVCPMemory, 118	FlyCapture2Managed::ManagedPGRGuid, 132
ReadGVCPRegister, 119	Equals, 133
ReadGVCPRegisterBlock, 119	GetHashCode, 133
SetGigEImageBinningSettings, 119	ManagedPGRGuid, 132, 133
SetGigEImageSettings, 119 SetGigEImageSettings, 119	operator=, 133
SetGigEImagingMode, 119	operator==, 133
octorgermagnigivioue, 117	operator—, 133

value0, 133	Lzw, 143
value1, 133	None, 143
value2, 133	PackBits, 143
value2, 133 value3, 133	TiffOption, 144
FlyCapture2Managed::ManagedUtilities, 134	FlyCapture2Managed::TimeStamp, 145
LaunchBrowser, 134	
	cycleCount, 145
LaunchCommand, 134	cycleOffset, 145
LaunchHelp, 134	cycleSeconds, 145
library Version, 134	microSeconds, 145
systemInfo, 134	seconds, 145
FlyCapture2Managed::PgmOption, 135	FlyCapture2Managed::Translate, 146
binaryFile, 135	ToMgd, 149
PgmOption, 135	ToNative, 149
FlyCapture2Managed::PngOption, 136	translate, 149
compressionLevel, 136	FlyCapture2Managed::TriggerMode, 150
interlaced, 136	mode, 150
PngOption, 136	onOff, 150
FlyCapture2Managed::PpmOption, 137	parameter, 150
binaryFile, 137	polarity, 150
PpmOption, 137	source, 150
FlyCapture2Managed::StrobeControl, 138	FlyCapture2Managed::TriggerModeInfo, 151
delay, 138	modeMask, 151
duration, 138	onOffSupported, 151
onOff, 138	polaritySupported, 151
polarity, 138	present, 151
source, 138	readOutSupported, 151
FlyCapture2Managed::StrobeInfo, 139	softwareTriggerSupported, 152
max Value, 139	sourceMask, 152
minValue, 139	valueReadable, 152
onOffSupported, 139	Focus
polaritySupported, 139	Enumerations, 23
present, 140	ForceIPAddressToCamera
readOutSupported, 140	FlyCapture2Managed::ManagedBusManager, 87
source, 140	frameCounter
FlyCapture2Managed::SystemInfo, 141	FlyCapture2Managed::EmbeddedImageInfo, 56
byteOrder, 141	FrameRate
cpuDescription, 141	Enumerations, 18, 23
driverList, 142	frameRate
gpuDescription, 142	FlyCapture2Managed::AviOption, 41
libraryList, 142	FrameRate120
numCpuCores, 142	Enumerations, 18
osDescription, 142	FrameRate15
osType, 142	Enumerations, 18
screenHeight, 142	FrameRate1_875
	Enumerations, 18
screenWidth, 142	
systemMemorySize, 142	FrameRate240
FlyCapture2Managed::TiffOption, 143	Enumerations, 18
AdobeDeflate, 143	FrameRate30
CcittFax3, 143	Enumerations, 18
CcittFax4, 143	FrameRate3_75
compression, 144	Enumerations, 18
CompressionMethod, 143	FrameRate60
Deflate, 143	Enumerations, 18
Jpeg, 143	FrameRate7_5

Enumerations, 18	GetHistogram
FrameRateFormat7	FlyCapture2Managed::ManagedImageStatistics, 131
Enumerations, 18	GetInterfaceTypeFromGuid
FromFileExtension	FlyCapture2Managed::ManagedBusManager, 89
Enumerations, 20	GetLUTBankInfo
	FlyCapture2Managed::ManagedCameraBase, 103
Gain	GetLUTChannel
Enumerations, 23	FlyCapture2Managed::ManagedCameraBase, 103
gain	GetLUTInfo
FlyCapture2Managed::EmbeddedImageInfo, 56	FlyCapture2Managed::ManagedCameraBase, 103
Gamma	GetMean
Enumerations, 23	FlyCapture2Managed::ManagedImageStatistics, 131
GBRG	GetMemoryChannel
Enumerations, 16	FlyCapture2Managed::ManagedCameraBase, 103
GetActiveLUTBank	GetMemoryChannelInfo
FlyCapture2Managed::ManagedCameraBase, 10	FlyCapture2Managed::ManagedCameraBase, 104
GetCameraFromIndex	GetNativeCamera
FlyCapture2Managed::ManagedBusManager, 88	, ,
GetCameraFromIPAddress	GetNativeImage
FlyCapture2Managed::ManagedBusManager, 88	, ,
GetCameraFromSerialNumber	GetNativeImageStatistics
FlyCapture2Managed::ManagedBusManager, 88	FlyCapture2Managed::ManagedImageStatistics, 131
GetCameraInfo	GetNumOfCameras
FlyCapture2Managed::ManagedCameraBase, 10	, ,
GetCameraSerialNumberFromIndex	GetNumOfDevices
FlyCapture2Managed::ManagedBusManager, 89	FlyCapture2Managed::ManagedBusManager, 90
GetChannelStatus	GetNumPixelValues
	131 FlyCapture2Managed::ManagedImageStatistics, 131
GetConfiguration	GetNumStreamChannels
FlyCapture2Managed::ManagedCameraBase, 10	FlyCapture2Managed::ManagedGigECamera, 118
GetDeviceFromIndex	GetPixelValueRange
FlyCapture2Managed::ManagedBusManager, 89	FlyCapture2Managed::ManagedImageStatistics, 131
GetEmbeddedImageInfo	GetProperty
FlyCapture2Managed::ManagedCameraBase, 10	FlyCapture2Managed::ManagedCameraBase, 104
GetFormat7Configuration	GetPropertyInfo
FlyCapture2Managed::ManagedCamera, 94	FlyCapture2Managed::ManagedCameraBase, 104
GetFormat7Info	GetRange
FlyCapture2Managed::ManagedCamera, 94	FlyCapture2Managed::ManagedImageStatistics, 131
GetGigEImageBinningSettings	GetRawNativeImagePointer
FlyCapture2Managed::ManagedGigECamera, 1	17 FlyCapture2Managed::ManagedImage, 126
GetGigEImageSettings	GetSelectedCameraGuids
FlyCapture2Managed::ManagedGigECamera, 1	17 FlyCapture2Managed::Gui::CameraSelectionDialog, 52
GetGigEImageSettingsInfo	GetStatistics
FlyCapture2Managed::ManagedGigECamera, 1	17 FlyCapture2Managed::ManagedImageStatistics, 131
GetGigEImagingMode	GetStrobe
FlyCapture2Managed::ManagedGigECamera, 1	17 FlyCapture2Managed::ManagedCameraBase, 105
GetGigEProperty	GetStrobeInfo
FlyCapture2Managed::ManagedGigECamera, 1	FlyCapture2Managed::ManagedCameraBase, 105
GetGigEStreamChannelInfo	GetTriggerMode
FlyCapture2Managed::ManagedGigECamera, 1	18 FlyCapture2Managed::ManagedCameraBase, 105
GetGPIOPinDirection	GetTriggerModeInfo
FlyCapture2Managed::ManagedCameraBase, 10	PlyCapture2Managed::ManagedCameraBase, 106
GetHashCode	GetVideoModeAndFrameRate
FlyCapture2Managed::ManagedPGRGuid, 133	FlyCapture2Managed::ManagedCamera, 94

GetVideoModeAndFrameRateInfo	Enumerations, 20
FlyCapture2Managed::ManagedCamera, 95	IidcFailed
GigE	Enumerations, 18
Enumerations, 20	iidcVersion
GigE_10000Base_T	FlyCapture2Managed::CameraInfo, 45
Enumerations, 16	Image saving structures., 27
GigE_1000Base_T	ImageCallbackDelegate
Enumerations, 16	FlyCapture2Managed, 39
GigE_100Base_T	ImageConsistencyError
Enumerations, 16	Enumerations, 18
	ImageConversionFailed
GigE_10Base_T	2
Enumerations, 16	Enumerations, 18
gigEMajorVersion	ImageEventCallback
FlyCapture2Managed::CameraInfo, 45	FlyCapture2Managed, 39
gigEMinorVersion	ImageFileFormat
FlyCapture2Managed::CameraInfo, 45	Enumerations, 20
GigEPropertyType	imageHStepSize
Enumerations, 18	FlyCapture2Managed::Format7Info, 66
GPIOPinState	FlyCapture2Managed::GigEImageSettingsInfo, 71
FlyCapture2Managed::EmbeddedImageInfo, 56	ImageLibraryFailure
gpuDescription	Enumerations, 18
FlyCapture2Managed::SystemInfo, 142	imageMetadata
GrabMode	FlyCapture2Managed::ManagedImage, 129
Enumerations, 19	imageVStepSize
grabMode	FlyCapture2Managed::Format7Info, 66
FlyCapture2Managed::FC2Config, 59	FlyCapture2Managed::GigEImageSettingsInfo, 71
GrabTimeout	Infinite
Enumerations, 19	Enumerations, 19
grabTimeout	InitFailed
FlyCapture2Managed::FC2Config, 59	Enumerations, 17
GRBG	inputBitDepth
Enumerations, 16	FlyCapture2Managed::LutData, 81
Green	InterfaceType
Enumerations, 23	Enumerations, 20
Grey	interfaceType
Enumerations, 23	FlyCapture2Managed::CameraInfo, 45
	interlaced
HeartbearTimeout	FlyCapture2Managed::PngOption, 136
Enumerations, 19	interPacketDelay
Heartbeat	FlyCapture2Managed::GigEStreamChannel, 75
Enumerations, 19	InvalidBuManager
height	Enumerations, 17
FlyCapture2Managed::Format7ImageSettings, 6	
FlyCapture2Managed::GigEImageSettings, 70	Enumerations, 18
Hide	InvalidMode
FlyCapture2Managed::Gui::CameraControlDiale	
hostPost	InvalidPacketSize
FlyCapture2Managed::GigEStreamChannel, 75	Enumerations, 18
HQLinear	InvalidParameter
Enumerations, 17	Enumerations, 17
Hue	InvalidSettings
Enumerations, 23	Enumerations, 17
	ipAddress
Ieee1394	FlyCapture2Managed::CameraInfo, 45

Iris	libraryVersion
Enumerations, 23	FlyCapture2Managed::ManagedUtilities, 134
isColorCamera	Lightness
FlyCapture2Managed::CameraInfo, 45	Enumerations, 23
IsConnected	LinuxX64
FlyCapture2Managed::ManagedCameraBase, 10	
IsNativeImageValid	LinuxX86
FlyCapture2Managed::ManagedImage, 126	Enumerations, 22
IsochAlreadyStarted	LittleEndian
Enumerations, 18	Enumerations, 17
•	LowLevelFailure
IsochBandwidthExceeded	
Enumerations, 18	Enumerations, 17
isochBusSpeed	LutFailed
FlyCapture2Managed::FC2Config, 59	Enumerations, 18
IsochFailed	Lzw
Enumerations, 18	FlyCapture2Managed::TiffOption, 143
IsochNotStarted	
Enumerations, 18	m_externalDelegate
IsochRetrieveBufferFailed	FlyCapture2Managed::ManagedCameraBase, 113
Enumerations, 18	m_internalDelegate
IsochStartFailed	FlyCapture2Managed::ManagedCameraBase, 113
Enumerations, 18	m_pNativeCamBase
IsochStopFailed	FlyCapture2Managed::ManagedCameraBase, 113
Enumerations, 18	Mac
IsochSyncFailed	Enumerations, 22
Enumerations, 18	macAddress
isReadable	FlyCapture2Managed::CameraInfo, 45
FlyCapture2Managed::GigEProperty, 73	major
IsVisible	FlyCapture2Managed::FC2Version, 62
FlyCapture2Managed::Gui::CameraControlDial	
	FlyCapture2Managed::ManagedAVIRecorder, 83
isWritable	ManagedBusManager ManagedBusManager
FlyCapture2Managed::GigEProperty, 73	FlyCapture2Managed::ManagedBusManager, 87
T _m	ManagedCallbackType
Jpeg	Enumerations, 20
Enumerations, 20	,
FlyCapture2Managed::TiffOption, 143	ManagedCamera
Jpeg2000	FlyCapture2Managed::ManagedCamera, 94
Enumerations, 20	ManagedCameraBase
JpegOption	FlyCapture2Managed::ManagedCameraBase, 101
FlyCapture2Managed::JpegOption, 79	ManagedGigECamera
Jpg2Option	FlyCapture2Managed::ManagedGigECamera, 117
FlyCapture2Managed::Jpg2Option, 80	ManagedImage
	FlyCapture2Managed::ManagedImage, 125
keyword	ManagedImageStatistics
FlyCapture2Managed::ConfigROM, 54	FlyCapture2Managed::ManagedImageStatistics, 131
• 1	ManagedPGRGuid
LaunchBrowser	FlyCapture2Managed::ManagedPGRGuid, 132, 133
FlyCapture2Managed::ManagedUtilities, 134	manualSupported
LaunchCommand	FlyCapture2Managed::CameraPropertyInfo, 50
FlyCapture2Managed::ManagedUtilities, 134	max
LaunchHelp	FlyCapture2Managed::CameraPropertyInfo, 50
FlyCapture2Managed::ManagedUtilities, 134	FlyCapture2Managed::GigEProperty, 73
libraryList	maxBytesPerPacket
	•
FlyCapture2Managed::SystemInfo, 142	FlyCapture2Managed::Format7PacketInfo, 68

maxHeight	Enumerations, 21
FlyCapture2Managed::Format7Info, 66	Mode2
FlyCapture2Managed::GigEImageSettingsInfo,	71 Enumerations, 21
maximumBusSpeed	Mode20
FlyCapture2Managed::CameraInfo, 45	Enumerations, 21
maxPacketSize	Mode21
FlyCapture2Managed::Format7Info, 66	Enumerations, 21
maxValue	Mode22
FlyCapture2Managed::StrobeInfo, 139	Enumerations, 21
maxWidth	Mode23
FlyCapture2Managed::Format7Info, 66	Enumerations, 21
FlyCapture2Managed::GigEImageSettingsInfo,	
Memory Allocation Failed	Enumerations, 21
Enumerations, 17	Mode25
microSeconds	Enumerations, 21
FlyCapture2Managed::TimeStamp, 145	Mode26
min Ely Continuo Managa du Compara Promorty Info 50	Enumerations, 21
FlyCapture2Managed::CameraPropertyInfo, 50	
FlyCapture2Managed::GigEProperty, 73	Enumerations, 21
minor	Mode28
FlyCapture2Managed::FC2Version, 62	Enumerations, 21
minPacketSize	Mode29
FlyCapture2Managed::Format7Info, 66	Enumerations, 21
minValue	Mode3
FlyCapture2Managed::StrobeInfo, 139	Enumerations, 21
Mode	Mode30
Enumerations, 20	Enumerations, 21
mode	Mode31
FlyCapture2Managed::Format7ImageSettings, 6	Enumerations, 21
FlyCapture2Managed::Format7Info, 66	Mode4
FlyCapture2Managed::TriggerMode, 150	Enumerations, 21
Mode0	Mode5
Enumerations, 21	Enumerations, 21
Mode1	Mode6
Enumerations, 21	Enumerations, 21
Mode10	Mode7
Enumerations, 21	Enumerations, 21
Model1	Mode8
Enumerations, 21	Enumerations, 21
Mode12	Mode9
Enumerations, 21	Enumerations, 21
Mode13	modelName
Enumerations, 21	FlyCapture2Managed::CameraInfo, 45
Mode14	modeMask
Enumerations, 21	FlyCapture2Managed::TriggerModeInfo, 151
Mode15	Try Captare 21 ranaged Trigger violatino, 131
Enumerations, 21	NearestNeighbor
Mode16	Enumerations, 17
Enumerations, 21	networkInterfaceIndex
Mode17	FlyCapture2Managed::GigEStreamChannel, 76
Enumerations, 21	NoColorProcessing
Mode18	Enumerations, 17
Enumerations, 21	node VendorId ElyContine 2 Manage du Config POM 54
Mode19	FlyCapture2Managed::ConfigROM, 54

None	Enumerations, 17
Enumerations, 16, 19	On
FlyCapture2Managed::TiffOption, 143	Enumerations, 16
NotConnected	onePush
Enumerations, 17	FlyCapture2Managed::CameraProperty, 48
NotFound	onePushSupported
Enumerations, 17	FlyCapture2Managed::CameraPropertyInfo, 50
NotImplemented	OnNativeCallback
Enumerations, 17	FlyCapture2Managed::ManagedCameraBase, 106
NotInFormat7	onOff
Enumerations, 18	FlyCapture2Managed::CameraProperty, 48
NotInitialized	FlyCapture2Managed::EmbeddedImageInfoProperty,
Enumerations, 17	FlyCapture2Managed::StrobeControl, 138
NotSupported	FlyCapture2Managed::TriggerMode, 150
Enumerations, 18	onOffSupported
numBanks	FlyCapture2Managed::CameraPropertyInfo, 51
FlyCapture2Managed::LutData, 81	FlyCapture2Managed::StrobeInfo, 139
NumberOfFrameRates	FlyCapture2Managed::TriggerModeInfo, 151
Enumerations, 18	operator=
NumberOfModes	FlyCapture2Managed::ManagedPGRGuid, 133
Enumerations, 21	operator==
NumberOfPixelFormats	FlyCapture2Managed::ManagedPGRGuid, 133
Enumerations, 22	osDescription
NumberOfStatisticsChannels	FlyCapture2Managed::SystemInfo, 142
Enumerations, 23	OSType
NumberOfVideoModes	Enumerations, 21
Enumerations, 24	osType
numBuffers	FlyCapture2Managed::SystemInfo, 142
FlyCapture2Managed::FC2Config, 59	outputBitDepth
numChannels	FlyCapture2Managed::LutData, 82
FlyCapture2Managed::GigEConfig, 69	
FlyCapture2Managed::LutData, 81	PackBits
numCpuCores	FlyCapture2Managed::TiffOption, 143
FlyCapture2Managed::SystemInfo, 142	PacketDelay
numEntries	Enumerations, 19
FlyCapture2Managed::LutData, 82	PacketSize
numImageNotifications	Enumerations, 19
FlyCapture2Managed::FC2Config, 59	packetSize
	FlyCapture2Managed::Format7Info, 66
Off	FlyCapture2Managed::GigEStreamChannel, 76
Enumerations, 16	Pan
offsetHStepSize	Enumerations, 23
FlyCapture2Managed::Format7Info, 66	parameter
FlyCapture2Managed::GigEImageSettingsInfo,	72 FlyCapture2Managed::TriggerMode, 150
offsetVStepSize	percentage
FlyCapture2Managed::Format7Info, 66	FlyCapture2Managed::Format7Info, 66
FlyCapture2Managed::GigEImageSettingsInfo,	•
offsetX	Enumerations, 20
FlyCapture2Managed::Format7ImageSettings, 6	• •
FlyCapture2Managed::GigEImageSettings, 70	FlyCapture2Managed::PgmOption, 135
offsetY	PixelFormat
FlyCapture2Managed::Format7ImageSettings, 6	
FlyCapture2Managed::GigEImageSettings, 70	pixelFormat
Ok	FlyCapture2Managed::Format7ImageSettings, 63

57

FlyCapture2Managed::GigEImageSettings, 70 FlyCapture2Managed::ManagedImage, 129	FlyCapture2Managed::CameraProperty, 48 FlyCapture2Managed::CameraPropertyInfo, 51
PixelFormat411Yuv8	FlyCapture2Managed::StrobeInfo, 140
Enumerations, 22	FlyCapture2Managed::TriggerModeInfo, 151
PixelFormat422Yuv8	progressive
Enumerations, 22	FlyCapture2Managed::JpegOption, 79
PixelFormat444Yuv8	PropertyFailed
Enumerations, 22	Enumerations, 18
PixelFormatBgr	PropertyNotPresent
Enumerations, 22	Enumerations, 18
PixelFormatBgru	PropertyType
Enumerations, 22	Enumerations, 22
pixelFormatBitField	
•	propType FlyConture2ManageduCigEPmanagty, 72
FlyCapture2Managed::Format7Info, 66	FlyCapture2Managed::GigEProperty, 73
FlyCapture2Managed::GigEImageSettingsInfo, PixelFormatMono12	
	quality Flactors 2 Managed a Lagrangian 70
Enumerations, 22	FlyCapture2Managed::JpegOption, 79
PixelFormatMono16	FlyCapture2Managed::Jpg2Option, 80
Enumerations, 22	QueryGigEImagingMode
PixelFormatMono8	FlyCapture2Managed::ManagedGigECamera, 118
Enumerations, 22	D.
PixelFormatRaw12	Raw
Enumerations, 22	Enumerations, 20
PixelFormatRaw16	ReadGVCPMemory
Enumerations, 22	FlyCapture2Managed::ManagedGigECamera, 118
PixelFormatRaw8	ReadGVCPRegister
Enumerations, 22	FlyCapture2Managed::ManagedGigECamera, 119
PixelFormatRgb	ReadGVCPRegisterBlock
Enumerations, 22	FlyCapture2Managed::ManagedGigECamera, 119
PixelFormatRgb16	readOutSupported
Enumerations, 22	FlyCapture2Managed::CameraPropertyInfo, 51
PixelFormatRgb8	FlyCapture2Managed::StrobeInfo, 140
Enumerations, 22	FlyCapture2Managed::TriggerModeInfo, 151
PixelFormatRgbu	ReadPhyRegister
Enumerations, 22	FlyCapture2Managed::ManagedBusManager, 90
PixelFormatSignedMono16	ReadRegister
Enumerations, 22	FlyCapture2Managed::ManagedCameraBase, 106
PixelFormatSignedRgb16	ReadRegisterBlock
Enumerations, 22	FlyCapture2Managed::ManagedCameraBase, 106
Png	ReadRegisterFailed
Enumerations, 20	Enumerations, 18
PngOption	recommendedBytesPerPacket
FlyCapture2Managed::PngOption, 136	FlyCapture2Managed::Format7PacketInfo, 68
	Red
polarity FlyContinue 2Manage du Strabe Control 128	
FlyCapture2Managed::StrobeControl, 138	Enumerations, 23
FlyCapture2Managed::TriggerMode, 150	RegisterCallback
polaritySupported	FlyCapture2Managed::ManagedBusManager, 90
FlyCapture2Managed::StrobeInfo, 139	RegisterFailed
FlyCapture2Managed::TriggerModeInfo, 151	Enumerations, 18
Ppm	ReleaseBuffer
Enumerations, 20	FlyCapture2Managed::ManagedImage, 126
PpmOption	Removal
FlyCapture2Managed::PpmOption, 137	Enumerations, 20
present	RescanBus

FlyCapture2Managed::ManagedBusManager, 90	SetData
RestoreFromMemoryChannel	FlyCapture2Managed::ManagedImage, 128
FlyCapture2Managed::ManagedCameraBase, 10	
RetrieveBuffer	FlyCapture2Managed::ManagedImage, 128
FlyCapture2Managed::ManagedCameraBase, 10	
RGGB	FlyCapture2Managed::ManagedCameraBase, 108
Enumerations, 16	SetFormat7Configuration
Rigorous	FlyCapture2Managed::ManagedCamera, 95
Enumerations, 17	SetGigEImageBinningSettings
ROIPosition	FlyCapture2Managed::ManagedGigECamera, 119
FlyCapture2Managed::EmbeddedImageInfo, 56	
rows	FlyCapture2Managed::ManagedGigECamera, 119
FlyCapture2Managed::ManagedImage, 129	SetGigEImagingMode
Try Cupture 21 runu ged runu ged mage, 129	FlyCapture2Managed::ManagedGigECamera, 119
S100	SetGigEProperty
Enumerations, 16	FlyCapture2Managed::ManagedGigECamera, 120
S1600	SetGigEStreamChannelInfo
Enumerations, 16	FlyCapture2Managed::ManagedGigECamera, 120
S200	SetGPIOPinDirection
Enumerations, 16	FlyCapture2Managed::ManagedCameraBase, 109
S3200	SetLUTChannel
Enumerations, 16	FlyCapture2Managed::ManagedCameraBase, 109
S400	• •
Enumerations, 16	SetProperty Fly Conture 2 Managed to Managed Compare Page 110
S480	FlyCapture2Managed::ManagedCameraBase, 110 SetStrobe
Enumerations, 16	
S800	FlyCapture2Managed::ManagedCameraBase, 110
	SetTriggerMode
Enumerations, 16	FlyCapture2Managed::ManagedCameraBase, 111
Saturation	SetVideoModeAndFrameRate
Enumerations, 23	FlyCapture2Managed::ManagedCamera, 96
Save	Sharpness
FlyCapture2Managed::ManagedImage, 126, 127	
SaveToMemoryChannel	Show
FlyCapture2Managed::ManagedCameraBase, 10	
screenHeight	ShowModal
FlyCapture2Managed::SystemInfo, 142	FlyCapture2Managed::Gui::CameraSelectionDialog, 52
screenWidth	Shutter
FlyCapture2Managed::SystemInfo, 142	Enumerations, 23
seconds	shutter
FlyCapture2Managed::TimeStamp, 145	FlyCapture2Managed::EmbeddedImageInfo, 56
sensorInfo	softwareTriggerSupported
FlyCapture2Managed::CameraInfo, 46	FlyCapture2Managed::TriggerModeInfo, 152
sensorResolution	source
FlyCapture2Managed::CameraInfo, 46	FlyCapture2Managed::StrobeControl, 138
serialNumber	FlyCapture2Managed::StrobeInfo, 140
FlyCapture2Managed::CameraInfo, 46	FlyCapture2Managed::TriggerMode, 150
SetActiveLUTBank	sourceMask
FlyCapture2Managed::ManagedCameraBase, 10	FlyCapture2Managed::TriggerModeInfo, 152
SetCallback	sourcePort
FlyCapture2Managed::ManagedCameraBase, 10	FlyCapture2Managed::GigEStreamChannel, 76
SetChannelStatus	StartCapture
FlyCapture2Managed::ManagedImageStatistics,	131 FlyCapture2Managed::ManagedCameraBase, 111
SetConfiguration	StatisticsChannel
FlyCapture2Managed::ManagedCameraBase, 10	Enumerations, 23

StopCapture FlyCapture2Managed::ManagedCameraBase, 11	FlyCapture2Managed::CameraPropertyInfo, 51
stride	FlyCapture2Managed::Format7PacketInfo, 68
FlyCapture2Managed::ManagedImage, 129	units
StrobeFailed	FlyCapture2Managed::CameraPropertyInfo, 51
Enumerations, 18	unitSpecId
strobePattern	FlyCapture2Managed::ConfigROM, 54
FlyCapture2Managed::EmbeddedImageInfo, 56	
Structures, 25	FlyCapture2Managed::ConfigROM, 54
subnetMask	unitSWVer
FlyCapture2Managed::CameraInfo, 46	FlyCapture2Managed::ConfigROM, 54
supported	Unknown
FlyCapture2Managed::LutData, 82	Enumerations, 16, 20
systemInfo	UnknownOS
FlyCapture2Managed::ManagedUtilities, 134	Enumerations, 22
systemMemorySize	UnregisterCallback
FlyCapture2Managed::SystemInfo, 142	FlyCapture2Managed::ManagedBusManager, 91
	Unspecified
Temperature	Enumerations, 16, 19, 23
Enumerations, 23	Unsupported
Tiff	Enumerations, 16
Enumerations, 20	Usb2
TiffOption	Enumerations, 20
FlyCapture2Managed::TiffOption, 144	userDefinedName
Tilt	FlyCapture2Managed::CameraInfo, 46
Enumerations, 23	
Timeout	ValidateFormat7Settings
Enumerations, 18	FlyCapture2Managed::ManagedCamera, 96
timeStamp	value
FlyCapture2Managed::ManagedImage, 129	FlyCapture2Managed::GigEProperty, 74
timestamp	value0
FlyCapture2Managed::EmbeddedImageInfo, 56	FlyCapture2Managed::ManagedPGRGuid, 133
ToMgd	value1
FlyCapture2Managed::Translate, 149	FlyCapture2Managed::ManagedPGRGuid, 133
ToNative	value2
FlyCapture2Managed::Translate, 149	FlyCapture2Managed::ManagedPGRGuid, 133
translate	value3
FlyCapture2Managed::Translate, 149	FlyCapture2Managed::ManagedPGRGuid, 133
	valueA
TriggerDelay	FlyCapture2Managed::CameraProperty, 48
Enumerations, 23	valueB
TriggerFailed	
Enumerations, 18	FlyCapture2Managed::CameraProperty, 48
TriggerMode	valueReadable
Enumerations, 23	FlyCapture2Managed::TriggerModeInfo, 152
Type	vendorName
FlyCapture2Managed::FC2Exception, 61	FlyCapture2Managed::CameraInfo, 46
type	vendorUniqueInfo0
FlyCapture2Managed::CameraProperty, 48	FlyCapture2Managed::ConfigROM, 54
FlyCapture2Managed::CameraPropertyInfo, 51	vendorUniqueInfo1
FlyCapture2Managed::FC2Version, 62	FlyCapture2Managed::ConfigROM, 54
	vendorUniqueInfo2
Undefined	FlyCapture2Managed::ConfigROM, 54
Enumerations, 17	vendorUniqueInfo3
unitAbbr	FlyCapture2Managed::ConfigROM, 54

VideoMode	Enumerations, 23
Enumerations, 23	whiteBalance
VideoMode1024x768Rgb	FlyCapture2Managed::EmbeddedImageInfo, 56
Enumerations, 24	width
VideoMode1024x768Y16	FlyCapture2Managed::Format7ImageSettings, 64
Enumerations, 24	FlyCapture2Managed::GigEImageSettings, 70
VideoMode1024x768Y8	Windows X64
Enumerations, 24	Enumerations, 22
VideoMode1024x768Yuv422	WindowsX86
Enumerations, 24	Enumerations, 22
VideoMode1280x960Rgb	WriteGVCPMemory
Enumerations, 24	FlyCapture2Managed::ManagedGigECamera, 120
VideoMode1280x960Y16	WriteGVCPRegister
Enumerations, 24	FlyCapture2Managed::ManagedGigECamera, 120
VideoMode1280x960Y8	WriteGVCPRegisterBlock
Enumerations, 24	FlyCapture2Managed::ManagedGigECamera, 121
VideoMode1280x960Yuv422	WritePhyRegister
Enumerations, 24	FlyCapture2Managed::ManagedBusManager, 91
VideoMode1600x1200Rgb	WriteRegister
Enumerations, 24	FlyCapture2Managed::ManagedCameraBase, 112
VideoMode1600x1200Y16	WriteRegisterBlock
Enumerations, 24	FlyCapture2Managed::ManagedCameraBase, 112
VideoMode1600x1200Y8	WriteRegisterFailed
Enumerations, 24	Enumerations, 18
VideoMode1600x1200Yuv422	ILIDI 1
Enumerations, 24	xmlURL1
VideoMode160x120Yuv444	FlyCapture2Managed::CameraInfo, 46
Enumerations, 24	xmlURL2
VideoMode320x240Yuv422	FlyCapture2Managed::CameraInfo, 46
Enumerations, 24	7
VideoMode640x480Rgb	Zoom
Enumerations, 24	Enumerations, 23
VideoMode640x480Y16	
Enumerations, 24	
VideoMode640x480Y8	
Enumerations, 24	
VideoMode640x480Yuv411	
Enumerations, 24	
VideoMode640x480Yuv422	
Enumerations, 24	
VideoMode800x600Rgb	
Enumerations, 24	
VideoMode800x600Y16	
Enumerations, 24	
VideoMode800x600Y8	
Enumerations, 24	
VideoMode800x600Yuv422	
Enumerations, 24	
VideoModeFormat7	
Enumerations, 24	
WaitForBufferEvent	
FlyCapture2Managed::ManagedCameraBase, 1	112
WhiteBalance	